

[MS-DSCPM-Diff]:

Desired State Configuration Pull Model Protocol

Intellectual Property Rights Notice for Open Specifications Documentation

- **Technical Documentation.** Microsoft publishes Open Specifications documentation (“this documentation”) for protocols, file formats, data portability, computer languages, and standards support. Additionally, overview documents cover inter-protocol relationships and interactions.
- **Copyrights.** This documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you can make copies of it in order to develop implementations of the technologies that are described in this documentation and can distribute portions of it in your implementations that use these technologies or in your documentation as necessary to properly document the implementation. You can also distribute in your implementation, with or without modification, any schemas, IDLs, or code samples that are included in the documentation. This permission also applies to any documents that are referenced in the Open Specifications documentation.
- **No Trade Secrets.** Microsoft does not claim any trade secret rights in this documentation.
- **Patents.** Microsoft has patents that might cover your implementations of the technologies described in the Open Specifications documentation. Neither this notice nor Microsoft's delivery of this documentation grants any licenses under those patents or any other Microsoft patents. However, a given Open Specifications document might be covered by the Microsoft [Open Specifications Promise](#) or the [Microsoft Community Promise](#). If you would prefer a written license, or if the technologies described in this documentation are not covered by the Open Specifications Promise or Community Promise, as applicable, patent licenses are available by contacting iplg@microsoft.com.
- **License Programs.** To see all of the protocols in scope under a specific license program and the associated patents, visit the [Patent Map](#).
- **Trademarks.** The names of companies and products contained in this documentation might be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights. For a list of Microsoft trademarks, visit www.microsoft.com/trademarks.
- **Fictitious Names.** The example companies, organizations, products, domain names, email addresses, logos, people, places, and events that are depicted in this documentation are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

Reservation of Rights. All other rights are reserved, and this notice does not grant any rights other than as specifically described above, whether by implication, estoppel, or otherwise.

Tools. The Open Specifications documentation does not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments, you are free to take advantage of them. Certain Open Specifications documents are intended for use in conjunction with publicly available standards specifications and network programming art and, as such, assume that the reader either is familiar with the aforementioned material or has immediate access to it.

Support. For questions and support, please contact dochelp@microsoft.com.

Revision Summary

Date	Revision History	Revision Class	Comments
8/8/2013	1.0	New	Released new document.
11/14/2013	2.0	Major	Updated and revised the technical content.
2/13/2014	2.1	Minor	Clarified the meaning of the technical content.
5/15/2014	2.1	None	No changes to the meaning, language, or formatting of the technical content.
6/30/2015	3.0	Major	Significantly changed the technical content.
10/16/2015	4.0	Major	Significantly changed the technical content.
7/14/2016	5.0	Major	Significantly changed the technical content.
6/1/2017	5.0	None	No changes to the meaning, language, or formatting of the technical content.
<u>9/15/2017</u>	<u>6.0</u>	<u>Major</u>	<u>Significantly changed the technical content.</u>

Table of Contents

1	Introduction	7
1.1	Glossary	7
1.2	References	8
1.2.1	Normative References	8
1.2.2	Informative References	8
1.3	Overview	8
1.4	Relationship to Other Protocols	8
1.5	Prerequisites/Preconditions	8
1.6	Applicability Statement	9
1.7	Versioning and Capability Negotiation	9
1.8	Vendor-Extensible Fields	9
1.9	Standards Assignments.....	9
2	Messages.....	10
2.1	Transport	10
2.2	Common Data Types	10
2.2.1	Namespaces	10
2.2.2	HTTP Headers	10
2.2.2.1	Content-Type	10
2.2.2.1.1	Application/octet-stream	11
2.2.2.1.2	Application/json	11
2.2.2.2	Checksum	11
2.2.2.3	ChecksumAlgorithm	11
2.2.2.4	ConfigurationName	11
2.2.2.5	ProtocolVersion.....	11
2.2.2.6	AgentId	12
2.2.2.7	Authorization.....	12
2.2.2.8	DSC-certificateRotation.....	12
2.2.3	Common URI Parameters	12
2.2.3.1	ConfigurationId.....	13
2.2.3.2	ModuleName	13
2.2.3.3	ModuleVersion	13
2.2.3.4	AgentId	13
3	Protocol Details.....	14
3.1	GetConfiguration Versions 1.0 and 1.1 Details	14
3.1.1	Abstract Data Model.....	14
3.1.2	Timers	14
3.1.3	Initialization.....	14
3.1.4	Higher-Layer Triggered Events	14
3.1.5	Message Processing Events and Sequencing Rules	14
3.1.5.1	Action(ConfigurationId={ConfigurationId})/ConfigurationContent	15
3.1.5.1.1	GET	15
3.1.5.1.1.1	Request Body	16
3.1.5.1.1.2	Response Body	16
3.1.5.1.1.3	Processing Details.....	16
3.1.6	Timer Events.....	17
3.1.7	Other Local Events.....	17
3.2	GetModule Versions 1.0 and 1.1 Details	17
3.2.1	Abstract Data Model.....	17
3.2.2	Timers	17
3.2.3	Initialization.....	17
3.2.4	Higher-Layer Triggered Events	17
3.2.5	Message Processing Events and Sequencing Rules	17

3.2.5.1	Module(ConfigurationId={ConfigurationId},ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent	18
3.2.5.1.1	GET	18
3.2.5.1.1.1	Request Body	19
3.2.5.1.1.2	Response Body	19
3.2.5.1.1.3	Processing Details	19
3.2.6	Timer Events.....	20
3.2.7	Other Local Events.....	20
3.3	GetAction Versions 1.0 and 1.1 Details	20
3.3.1	Abstract Data Model.....	20
3.3.2	Timers	20
3.3.3	Initialization.....	20
3.3.4	Higher-Layer Triggered Events	20
3.3.5	Message Processing Events and Sequencing Rules	20
3.3.5.1	Action(ConfigurationId={ConfigurationId})/GetAction	20
3.3.5.1.1	POST	21
3.3.5.1.1.1	Request Body	22
3.3.5.1.1.2	Response Body	22
3.3.5.1.1.3	Processing Details	22
3.3.6	Timer Events.....	22
3.3.7	Other Local Events.....	22
3.4	SendStatusReport Versions 1.0 and 1.1 Details.....	22
3.4.1	Abstract Data Model.....	22
3.4.2	Timers	23
3.4.3	Initialization.....	23
3.4.4	Higher-Layer Triggered Events	23
3.4.5	Message Processing Events and Sequencing Rules	23
3.4.5.1	Node(ConfigurationID={ConfigurationId})/SendStatusReport.....	23
3.4.5.1.1	POST	23
3.4.5.1.1.1	Request Body	24
3.4.5.1.1.2	Response Body	25
3.4.5.1.1.3	Processing Details	25
3.4.6	Timer Events.....	25
3.4.7	Other Local Events.....	25
3.5	GetStatusReport Versions 1.0 and 1.1 Details.....	25
3.5.1	Abstract Data Model.....	25
3.5.2	Timers	25
3.5.3	Initialization.....	25
3.5.4	Higher-Layer Triggered Events	26
3.5.5	Message Processing Events and Sequencing Rules	26
3.5.5.1	Node(ConfigurationId={ConfigurationId})/StatusReports.....	26
3.5.5.1.1	GET	26
3.5.5.1.1.1	Request Body	27
3.5.5.1.1.2	Response Body	27
3.5.5.1.1.3	Processing Details	27
3.5.6	Timer Events.....	27
3.5.7	Other Local Events.....	27
3.6	GetConfiguration Version 2.0 Details	28
3.6.1	Abstract Data Model.....	28
3.6.2	Timers	28
3.6.3	Initialization.....	28
3.6.4	Higher-Layer Triggered Events	28
3.6.5	Message Processing Events and Sequencing Rules	28
3.6.5.1	Nodes(AgentId={AgentId})/ Configurations(ConfigurationName={ConfigurationName})/ConfigurationContent	29
3.6.5.2	GET.....	29

3.6.5.2.1	Request Body.....	30
3.6.5.2.2	Response Body	30
3.6.5.2.3	Processing Details	30
3.6.6	Timer Events.....	31
3.6.7	Other Local Events.....	31
3.7	GetModule Version 2.0 Details	31
3.7.1	Abstract Data Model.....	31
3.7.2	Timers	31
3.7.3	Initialization.....	31
3.7.4	Higher-Layer Triggered Events	31
3.7.5	Message Processing Events and Sequencing Rules	31
3.7.5.1	Modules(ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent	32
3.7.5.1.1	GET	32
3.7.5.1.1.1	Request Body	34
3.7.5.1.1.2	Response Body	34
3.7.5.1.1.3	Processing Details.....	34
3.7.6	Timer Events.....	34
3.7.7	Other Local Events.....	34
3.8	GetDscAction Version 2.0 Details	34
3.8.1	Abstract Data Model.....	34
3.8.2	Timers	34
3.8.3	Initialization.....	34
3.8.4	Higher-Layer Triggered Events	34
3.8.5	Message Processing Events and Sequencing Rules	34
3.8.5.1	Nodes(AgentId={AgentId})/GetDscAction	35
3.8.5.1.1	POST	35
3.8.5.1.1.1	Request Body	36
3.8.5.1.1.2	Response Body	36
3.8.5.1.1.3	Processing Details.....	37
3.8.6	Timer Events.....	37
3.8.7	Other Local Events.....	37
3.9	RegisterDscAgent Version 2 Details	37
3.9.1	Abstract Data Model.....	37
3.9.2	Timers	37
3.9.3	Initialization.....	37
3.9.4	Higher-Layer Triggered Events	37
3.9.5	Message Processing Events and Sequencing Rules	37
3.9.5.1	Nodes(AgentId={AgentId})	38
3.9.5.1.1	PUT	38
3.9.5.1.1.1	Request Body	39
3.9.5.1.1.2	Response Body	39
3.9.5.1.1.3	Processing Details.....	39
3.9.6	Timer Events.....	39
3.9.7	Other Local Events.....	39
3.10	SendReport Version 2.0 Details.....	40
3.10.1	Abstract Data Model.....	40
3.10.2	Timers	40
3.10.3	Initialization.....	40
3.10.4	Higher-Layer Triggered Events	40
3.10.5	Message Processing Events and Sequencing Rules	40
3.10.5.1	Nodes(AgentID={AgentId})/SendReport	40
3.10.5.1.1	POST	40
3.10.5.1.1.1	Request Body	42
3.10.5.1.1.2	Response Body	42
3.10.5.1.1.3	Processing Details.....	42
3.10.6	Timer Events.....	42

3.10.7	Other Local Events.....	42
3.11	GetReports Version 2.0 Details	43
3.11.1	Abstract Data Model.....	43
3.11.2	Timers	43
3.11.3	Initialization.....	43
3.11.4	Higher-Layer Triggered Events	43
3.11.5	Message Processing Events and Sequencing Rules	43
3.11.5.1	Nodes(AgentId={AgentId})/Reports	43
3.11.5.1.1	GET	43
3.11.5.1.1.1	Request Body	45
3.11.5.1.1.2	Response Body	45
3.11.5.1.1.3	Processing Details.....	45
3.11.6	Timer Events.....	45
3.11.7	Other Local Events.....	45
3.12	CertificateRotation Details	45
3.12.1	Abstract Data Model.....	45
3.12.2	Timers	45
3.12.3	Initialization.....	45
3.12.4	Higher-Layer Triggered Events	45
3.12.5	Message Processing Events and Sequencing Rules	45
3.12.5.1	Nodes(AgentId={AgentId})/CertificateRotation	46
3.12.5.1.1	POST	46
3.12.5.1.1.1	Request Body	47
3.12.5.1.1.2	Response Body	47
3.12.5.1.1.3	Processing Details.....	47
3.12.6	Timer Events.....	47
3.12.7	Other Local Events.....	47
4	Protocol Examples	48
4.1	GetConfiguration Sequence	48
4.2	GetModule Sequence	48
4.3	GetAction Sequence	49
4.4	SendStatusReport Sequence.....	50
4.5	GetStatusReport Sequence.....	51
4.6	RegisterDscAgent Sequence	52
4.7	SendReport Sequence.....	53
4.8	GetDscAction Sequence	53
5	Security.....	55
5.1	Security Considerations for Implementers	55
5.2	Index of Security Parameters	55
6	Appendix A: Full JSON Schema.....	56
7	Appendix B: Product Behavior	60
8	Change Tracking.....	62
9	Index.....	63

1 Introduction

The Desired State Configuration Pull Model Protocol is based on the Hypertext Transfer Protocol (HTTP) (as specified in [RFC2616]). It is used for getting a client's configuration and modules from the server and for reporting back the client's status to the server.

Sections 1.5, 1.8, 1.9, 2, and 3 of this specification are normative. All other sections and examples in this specification are informative.

1.1 Glossary

This document uses the following terms:

Augmented Backus-Naur Form (ABNF): A modified version of Backus-Naur Form (BNF), commonly used by Internet specifications. ABNF notation balances compactness and simplicity with reasonable representational power. ABNF differs from standard BNF in its definitions and uses of naming rules, repetition, alternatives, order-independence, and value ranges. For more information, see [RFC5234].

binary large object (BLOB): A collection of binary data stored as a single entity in a database.

checksum: A value that is the summation of a byte stream. By comparing the checksums computed from a data item at two different times, one can quickly assess whether the data items are identical.

configuration: Represents a binary large object (BLOB). The protocol does not process the content of the BLOB and it is passed as-is to the higher layer.

Hypertext Transfer Protocol (HTTP): An application-level protocol for distributed, collaborative, hypermedia information systems (text, graphic images, sound, video, and other multimedia files) on the World Wide Web.

module: A BLOB in the Desired State Configuration Pull Model Protocol [MS-DSCPM]. The protocol does not process the content of the BLOB, and it is passed as it is to the higher layer.

Transmission Control Protocol (TCP): A protocol used with the Internet Protocol (IP) to send data in the form of message units between computers over the Internet. TCP handles keeping track of the individual units of data (called packets) that a message is divided into for efficient routing through the Internet.

Uniform Resource Identifier (URI): A string that identifies a resource. The URI is an addressing mechanism defined in Internet Engineering Task Force (IETF) Uniform Resource Identifier (URI): Generic Syntax [RFC3986].

Uniform Resource Locator (URL): A string of characters in a standardized format that identifies a document or resource on the World Wide Web. The format is as specified in [RFC1738].

universally unique identifier (UUID): A 128-bit value. UUIDs can be used for multiple purposes, from tagging objects with an extremely short lifetime, to reliably identifying very persistent objects in cross-process communication such as client and server interfaces, manager entry-point vectors, and RPC objects. UUIDs are highly likely to be unique. UUIDs are also known as globally unique identifiers (GUIDs) and these terms are used interchangeably in the Microsoft protocol technical documents (TDs). Interchanging the usage of these terms does not imply or require a specific algorithm or mechanism to generate the UUID. Specifically, the use of this term does not imply or require that the algorithms described in [RFC4122] or [C706] must be used for generating the UUID.

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as defined in [RFC2119]. All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

Links to a document in the Microsoft Open Specifications library point to the correct section in the most recently published version of the referenced document. However, because individual documents in the library are not updated at the same time, the section numbers in the documents may not match. You can confirm the correct section numbering by checking the Errata.

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information.

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <http://www.rfc-editor.org/rfc/rfc2119.txt>

[RFC2616] Fielding, R., Gettys, J., Mogul, J., et al., "Hypertext Transfer Protocol -- HTTP/1.1", RFC 2616, June 1999, <http://www.rfc-editor.org/rfc/rfc2616.txt>

[RFC4122] Leach, P., Mealling, M., and Salz, R., "A Universally Unique Identifier (UUID) URN Namespace", RFC 4122, July 2005, <http://www.rfc-editor.org/rfc/rfc4122.txt>

[RFC4234] Crocker, D., Ed., and Overell, P., "Augmented BNF for Syntax Specifications: ABNF", RFC 4234, October 2005, <http://www.rfc-editor.org/rfc/rfc4234.txt>

[RFC4634] Eastlake III, D. and Hansen, T., "US Secure Hash Algorithms (SHA and HMAC-SHA)", RFC 4634, July 2006, <http://www.ietf.org/rfc/rfc4634.txt>

[RFC4648] Josefsson, S., "The Base16, Base32, and Base64 Data Encodings", RFC 4648, October 2006, <http://www.rfc-editor.org/rfc/rfc4648.txt>

1.2.2 Informative References

None.

1.3 Overview

The Desired State Configuration Pull Model Protocol is used to register a client, to get the configuration and the module from the server, and to report back some elements to the server.

The protocol depends on HTTP for the transfer of all protocol messages, including the transfer of the binary data. In this specification, the entity that initiates the HTTP connection is referred to as the client, and the entity that responds to the HTTP connection is referred to as the server. With the Desired State Configuration Pull Model Protocol, binary data flows from the server to the client.

1.4 Relationship to Other Protocols

This protocol depends on HTTP as specified in [RFC2616]. HTTP version 1.1 is used with this protocol.

1.5 Prerequisites/Preconditions

This protocol does not provide a mechanism for a client to discover the Uniform Resource Locator (URL) of the server. Thus, it is a prerequisite that the client obtain the URL of the server before this protocol can be used.

1.6 Applicability Statement

The Desired State Configuration Pull Model Protocol is capable of downloading the configuration and modules from the server.

This document covers versioning issues in the following areas:

Supported Transports: This protocol can be implemented on top of HTTP, as specified in section 2.1.

Security and Authentication Methods: This protocol supports HTTP access authentication, as specified in [RFC2616] section 11.

Localization: This specification does not specify any localization-dependent protocol behavior.

1.7 Versioning and Capability Negotiation

None.

~~1.7~~**1.8 Vendor-Extensible Fields**

None.

~~1.8~~**1.9 Standards Assignments**

None.

2 Messages

2.1 Transport

The Desired State Configuration Pull Model Protocol uses HTTP 1.1, as specified in [RFC2616], as the transport layer.

A Transmission Control Protocol (TCP) port has not been reserved for this protocol. TCP port 80 is commonly used because many HTTP proxy servers forward only HTTP traffic that uses port 80.

The protocol uses the access authentication functionality of the HTTP layer as specified in [RFC2616] section 11.

2.2 Common Data Types

None.

2.2.1 Namespaces

None.

2.2.2 HTTP Headers

The Desired State Configuration Pull Model Protocol uses existing headers as specified in [RFC2616].

Unless specified otherwise, the headers defined in this specification are used in both request and response messages.

If a client or server receives an HTTP header that is not defined in this section, or if the header is not defined in the current context (for example, receiving a request-only header in a response), the header **MUST** be interpreted as specified in [RFC2616].

This section defines the syntax of the HTTP headers that use the Augmented Backus-Naur Form (ABNF) syntax, as specified in [RFC4234].

The following table summarizes the HTTP headers defined by this specification.

Header	Description
Content-Type	Section 2.2.2.1
Checksum	Section 2.2.2.2

2.2.2.1 Content-Type

The Content-Type header specifies the type of data that is included in the body of the GET or POST request.

The syntax of the Content-Type header is defined as follows.

```
Content-Type = "Content-Type: " "application/octet-stream" CRLF /  
              "Content-Type: " "application/json" [";charset=UTF-8"] CRLF
```

Example: Content-Type: application/octet-stream

Content-Type: application/json;charset=UTF-8

2.2.2.1.1 Application/octet-stream

This Content-Type is defined only for use in a request sent to the server and used in a GET response to get the module or configuration from a server.

2.2.2.1.2 Application/json

This Content-Type is defined only for use in a request sent to the server and used in a POST response.

2.2.2.2 Checksum

The Checksum header field is defined only for use in a response message sent to a client as part of a GET request for the module and configuration.

```
Checksum = "Checksum" : DQUOTE Check-sumvalue DQUOTE CRLF
Check-sumvalue = BASE16 ; specified in [RFC4648]
/ 0x00 (Null Character)
```

Example: "Checksum": "8eDMbsSDig15Xx+B3msvRrDa5N1njaf5smVujQjhOeI="

"Checksum": ""

2.2.2.3 ChecksumAlgorithm

The ChecksumAlgorithm header field specifies the checksum algorithm used to generate the checksum.

```
ChecksumAlgorithm = "ChecksumAlgorithm" : DQUOTE Check-sumAlgorithmvalue DQUOTE CRLF
Check-sumAlgorithmvalue = "SHA-256" ; specified in [RFC4634]
```

Example: "ChecksumAlgorithm": "SHA-256"

2.2.2.4 ConfigurationName

The ConfigurationName header field SHOULD<1> be used in the request message sent to the server as part of a GET request for the configuration.

```
ConfigurationName = "ConfigurationName" : DQUOTE Configuration-Namevalue DQUOTE CRLF
Configuration-Namevalue = Element *(Element)
Element = DIGIT / ALPHA
```

Example: "ConfigurationName": "SubPart1"

2.2.2.5 ProtocolVersion

The ProtocolVersion header field SHOULD<2> be used in the request message sent to the server as part of every request. The current version is hardcoded to 2.0.

```
ProtocolVersion = "ProtocolVersion" : DQUOTE ProtocolVersion-Namevalue DQUOTE CRLF
ProtocolVersion-Namevalue = Element . *(Element)
Element = DIGIT
```

Example: "ProtocolVersion": "2.0"

2.2.2.6 AgentId

The AgentId header field SHOULD<3> be used in the request message sent to the server as part of every request. The AgentId is a unique GUID value generated once and stored in the Registry.

```
AgentId = "AgentId" : DQUOTE AgentId-Namevalue DQUOTE CRLF
AgentId-Namevalue = Element *(Element)
Element = DIGIT / ALPHA / "-"
```

Example: "AgentId": "34C8104D-F7BA-4672-8226-0809B0A3BEC3"

2.2.2.7 Authorization

The Authorization header field SHOULD<4> be used in the request message sent to the server as part of every request. The Shared authorization key is generated during the registration and serves to verify the payload sent to the server.

```
Authorization = "Authorization": Shared DQUOTE Authorization-Namevalue DQUOTE CRLF
Authorization-Namevalue = A signature generated from an HMAC hash of the request body.
Element = DIGIT / ALPHA / "-" / "+"
```

Example: "Authorization": "Shared GKtPgozce1AM/pgc3LQzyGpDCRs15KoKx/2eXxIL8+w="

2.2.2.8 DSC-certificateRotation

The server MAY<5> send a DSC-certificateRotation response header field for every message sent to the client except for **CertificateRotation** (section 3.12) and **RegisterDscAgent** (section 3.9) responses. The only allowed value is "True". All other values are reserved. The value "True" indicates that the client SHOULD attempt the **CertificateRotation** message.

```
DSC-certificateRotation = "DSC-certificateRotation": DQUOTE DSC-certificateRotation-Namevalue
DQUOTE CRLF
DSC-certificateRotation-Namevalue = "True"
```

2.2.3 Common URI Parameters

The following table summarizes the set of common URI parameters defined by this protocol.

URI parameter	Section
ConfigurationId	Section 2.2.3.1
ModuleName	Section 2.2.3.2
ModuleVersion	Section 2.2.3.3

2.2.3.1 ConfigurationId

The *ConfigurationId* parameter is a universally unique identifier (UUID) as specified in [RFC4122] section 3.

2.2.3.2 ModuleName

The *ModuleName* parameter is a string that is used by the server to identify a specific module.

MODULENAME = Element *(Element)

Element = DIGIT / ALPHA / 0x5f

2.2.3.3 ModuleVersion

The *ModuleVersion* parameter identifies the version of a module. It can be either an empty string or a string containing two to four groups of digits where the groups are separated by a period.

```
MODULEVERSION = MULTIDIGIT 0x2E MULTIDIGIT
/ MULTIDIGIT 0x2E MULTIDIGIT 0x2E MULTIDIGIT
/ MULTIDIGIT 0x2E MULTIDIGIT 0x2E MULTIDIGIT 0x2E MULTIDIGIT
/ 0x00 (NULL character)
MULTIDIGIT = DIGIT *[DIGIT]
```

2.2.3.4 AgentId

The *AgentId* parameter SHOULD<6> be used in the request message sent to the server as part of every request. The AgentId is a unique GUID value generated once and stored in the Registry.

AgentId: "AgentId" : DQUOTE AgentId-Namevalue DQUOTE CRLF

AgentId-Namevalue: Element . *(Element)

Element: DIGIT / ALPHA

Example: "AgentId": "{34C8104D-F7BA-4672-8226-0809B0A3BEC3}"

3 Protocol Details

3.1 GetConfiguration Versions 1.0 and 1.1 Details

The purpose of the GetConfiguration request is to get the configuration from the server. The GetConfiguration request maps to an HTTP GET request in which the Content-Type header is an application/octet-stream.

3.1.1 Abstract Data Model

The server MUST maintain a **ConfigurationTable** where each entry contains:

ServerConfigurationId: A unique combination of a ConfigurationId (section 2.2.3.1) and a ConfigurationName (section 2.2.2.4). The ConfigurationId MUST NOT be empty.

ServerConfigurationData: A binary large object (BLOB). This data is not interpreted as part of this protocol and is passed on to higher layers as is.

3.1.2 Timers

None.

3.1.3 Initialization

None.

3.1.4 Higher-Layer Triggered Events

None.

3.1.5 Message Processing Events and Sequencing Rules

The server MUST match the ConfigurationId from the URL and, if specified, the ConfigurationName from the headers with the **ServerConfigurationId** in the **ConfigurationTable**. The server MUST use case-insensitive ordinal comparison to match the ConfigurationId (section 2.2.3.1) and ConfigurationName (section 2.2.2.4). If a match is found, the server MUST return **ConfigurationData** to the client with status code 200. If a match is not found, the server MUST return status code 404.

Resource	Description
Action(ConfigurationId={ConfigurationId})/ConfigurationContent	Gets the configuration from the server.

Request header	Usage	Value
ConfigurationName	Optional	As specified in section 2.2.2.4.

The responses to all the methods can result in the following status codes.

Status code	Reason phrase	Description
200	OK	Returned when the request is completed.

Status code	Reason phrase	Description
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
404	NOT FOUND	Returned when the resource is not found.

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
checksum	Required	As specified in section 2.2.2.2.
checksumalgorithm	Required	As specified in section 2.2.2.3.

3.1.5.1 Action(ConfigurationId={ConfigurationId})/ConfigurationContent

The following HTTP method is allowed to be performed on this resource.

HTTP method	Description
GET	Gets the configuration from the server.

3.1.5.1.1 GET

The URL specified by the client in the HTTP request line of the GET request identifies a "configuration point" targeted for the client. The server can have multiple configuration points and different configuration points can have different access permissions associated with them. For example, some configuration points require HTTP access authentication (as specified in [RFC2616] section 11). As another example, a configuration point could also allow only clients that connect from a specific IP address.

The syntax of the GetConfiguration request is defined as follows.

```

DSC-GetConfiguration-Request      = DSC-GetConfiguration-Req-Line
                                   DSC-GetConfigurationSetReq-Headers

DSC-GetConfiguration-Req-Line    = "GET" SP Request-URI SP HTTP-Version CRLF

Request-URI = Request-URI-Start DSC-GetConfigurationRequest-URI-End

DSC-GetConfigurationSetReq-Headers = *( DSC-GetConfigurationSetReq-Header-REQ
    / DSC-GetConfigurationSetReq-Header-OPT )

DSC-GetConfigurationSetReq-Header-REQ    = Host      ; section 14.23 of [RFC2616]

DSC-GetConfigurationSetReq-Header-OPT    = Connection ; section 14.10 of [RFC2616]
    / ConfigurationName ; section 2.2.2.4

DSC-GetConfigurationRequest-URI-End = "Action(ConfigurationId=" SQUOTE CONFIGURATIONID SQUOTE

RBRACKET FSLASH "ConfigurationContent"
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
CONFIGURATIONID = UUID ; as specified in [RFC4122]

```

The syntax of the GetConfiguration response is defined as follows:

```
DSC-GetConfiguration-Response = Status-Line
DSC-GetConfigurationResp-Headers
DSC-GetConfigurationResp-Body

DSC-GetConfigurationResp-Headers = *( DSC-GetConfigurationResp-Header-REQ
                                        / DSC-GetConfigurationResp-Header-OPT
                                        / DSC-GetConfigurationResp-Body)

DSC-GetConfigurationResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
                                        / Content-Type ; section 2.2.2.1.1
                                        / Checksum ; section 2.2.2.2
                                        / ChecksumAlgorithm ; section 2.2.2.3

DSC-GetConfigurationResp-Header-OPT = Server ; section 14.38 of [RFC2616]

DSC-GetConfigurationResp-Body = Configuration ; section 3.1.5.2.2
```

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
checksum	Required	As specified in section 2.2.2.2.
checksumalgorithm	Required	As specified in section 2.2.2.3.

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.1.5.1.1.1 Request Body

None.

3.1.5.1.1.2 Response Body

In the response body, configuration represents a BLOB.

3.1.5.1.1.3 Processing Details

The client gets the configuration from the server as content-type application/octet-stream in the response body for the GetConfiguration request. The server MUST send the checksum in the response headers as specified in section 2.2.2.2. The server MUST send the ChecksumAlgorithm in the response headers as specified in section 2.2.2.3. The server MUST generate the checksum using the following algorithm:

- Use the algorithm specified in section 2.2.2.3 to compute the hash of the response body as specified in [RFC4634] section 4.1.
- Perform base16 encoding of the computed hash as specified in [RFC4648] section 8.

3.1.6 Timer Events

None.

3.1.7 Other Local Events

None.

3.2 GetModule Versions 1.0 and 1.1 Details

The GetModule request gets the module from the server. The GetModule request maps to HTTP GET request with content-type as application/octet-stream as part of the request.

3.2.1 Abstract Data Model

The server MUST maintain a **ModuleTable** in which each entry contains the following:

ServerConfigurationId: The ConfigurationId (section 2.2.3.1).

ServerModuleName: The ModuleName (section 2.2.3.2).

ServerModuleVersion: The ModuleVersion (section 2.2.3.3).

ServerModuleData: A BLOB of data. This data is not interpreted as part of this protocol and is passed on to higher layers as is.

3.2.2 Timers

None.

3.2.3 Initialization

None.

3.2.4 Higher-Layer Triggered Events

None.

3.2.5 Message Processing Events and Sequencing Rules

The server MUST match ConfigurationId from the URL with **ServerConfigurationId**, ModuleName with **ServerModuleName**, and ModuleVersion with **ServerModuleVersion** of the **ModuleTable**. The server uses case-insensitive ordinal comparison to match ConfigurationId, ModuleName, and ModuleVersion. For a **ServerConfigurationId**, the server MUST have a unique combination of **ServerModuleName** and **ServerModuleVersion**. **ServerModuleName** in the **ModuleTable** MUST NOT be empty. If a match is found, the server returns **ModuleData** to the client with status code 200. If a match is not found, the server returns status code 404.

Resource	Description
Module(ConfigurationId={ConfigurationId},ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent	Get the module from the server.

The responses to all the methods can result in the following status codes.

Status code	Reason phrase	Description
200	OK	Request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
404	NOT FOUND	Used in cases where the resource is not found.

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
Checksum	Required	As specified in section 2.2.2.2.
ChecksumAlgorithm	Required	As specified in section 2.2.2.3.

3.2.5.1 Module(ConfigurationId={ConfigurationId},ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent

The following HTTP method is allowed to be performed on this resource.

HTTP method	Description
GET	Gets the module from the server.

3.2.5.1.1 GET

The URL specified by the client in the HTTP request line of the GET request identifies a "module point" targeted for the client. The server might have multiple module points and different modules points can have different access permissions associated with them. For example, some module points require HTTP access authentication (as specified in [RFC2616] section 11). Other module points allow only clients that connect from a specific IP address.

The syntax of the GetModule request is defined as follows.

```

DSC-GetModule-Request      = DSC-GetModule-Req-Line
                           DSC-GetModuleSetReq-Headers

DSC-GetModule-Req-Line    = "GET" SP Request-URI SP HTTP-Version CRLF
Request-URI                = Request-URI-Start DSC-GetModuleRequest-URI-End
DSC-GetModuleSetReq-Headers = *( DSC-GetModuleSetReq-Header-REQ
    / DSC-GetModuleSetReq-Header-OPT )

DSC-GetModuleSetReq-Header-REQ    = Host      ; section 14.23 of [RFC2616]

DSC-GetModuleSetReq-Header-OPT    = Connection ; section 14.10 of [RFC2616]
DSC-GetModuleRequest-URI-End      = "Module(ConfigurationId=" SQUOTE CONFIGURATIONID SQUOTE
    ",ModuleName=" SQUOTE MODULENAME SQUOTE
    ",ModuleVersion=" SQUOTE MODULEVERSION SQUOTE
    RBRACKET FSLASH "ModuleContent"

SQUOTE = %x27 ; ' (Single Quote)
MODULENAME = ModuleName; as specified in section 2.2.3.2
MODULEVERSION = *(DIGIT)[ 0x2E *(DIGIT)]; as specified in section 2.2.3.3

```

```

RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
CONFIGURATIONID = UUID ; as specified in [RFC4122]

```

The syntax of the GetModule response is defined as follows:

```

DSC-GetModule-Response = Status-Line
                        DSC-GetModuleResp-Headers
                        DSC-GetModuleResp-Body

DSC-GetModuleResp-Headers = *( DSC-GetModuleResp-Header-REQ
                               / DSC-GetModuleResp-Header-OPT)

DSC-GetModuleResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
                               / Content-Type ; section 2.2.2.1.1
                               / Checksum ; section 2.2.2.2
                               / ChecksumAlgorithm ; section 2.2.2.3

DSC-GetModuleResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-GetModuleResp-Body = ModuleData ; section 3.2.5.1.1.2

```

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
checksum	Required	As specified in section 2.2.2.2.
checksumalgorithm	Required	As specified in section 2.2.2.3.

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.2.5.1.1.1 Request Body

None.

3.2.5.1.1.2 Response Body

ModuleData represents a binary large object (BLOB) .

3.2.5.1.1.3 Processing Details

The client gets the module from the server as content-type application/octet-stream in the response body for GetModule request. The server MUST send the checksum in response headers as specified in section 2.2.2.2. The server MUST send the ChecksumAlgorithm in the response headers as specified in section 2.2.2.3. The server generates the checksum using the following algorithm:

- Use the algorithm specified in ChecksumAlgorithm to compute the hash of the response body as specified in [RFC4634] section 4.1.

- Perform base16 encoding of the computed hash as specified in [RFC4648] in section 8.

3.2.6 Timer Events

None.

3.2.7 Other Local Events

None.

3.3 GetAction Versions 1.0 and 1.1 Details

The purpose of the GetAction request is to get the action, as specified in section 3.3.5.1.1.2, from the server. GetAction request maps to HTTP POST request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.3.1 Abstract Data Model

None.

3.3.2 Timers

None.

3.3.3 Initialization

None.

3.3.4 Higher-Layer Triggered Events

None.

3.3.5 Message Processing Events and Sequencing Rules

Resource	Description
Action(ConfigurationId={ConfigurationId})/GetAction	Get the action from the server.

The responses to all the methods can result in the following status codes.

Status code	Reason phrase	Description
200	OK	The Request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
404	NOT FOUND	The resource is not found.

3.3.5.1 Action(ConfigurationId={ConfigurationId})/GetAction

The following HTTP method can be performed on this resource.

HTTP method	Description
POST	POSTs the data to the server and gets action from the server.

3.3.5.1.1 POST

The URL specified by the client in the HTTP request line of the POST request identifies the action point targeted for the client. The server can have multiple action points and different action points can have different access permissions associated with them. For example, some action points require HTTP access authentication (as specified in [RFC2616] section 11). Or, action points can also allow only clients that connect from a specific IP address.

The syntax of the GetAction request is defined as follows.

```

DSC-GetAction-Request = DSC-GetAction-Req-Line
                        DSC-GetActionSetReq-Headers
                        DSC-GetActionReq-Body

DSC-GetAction-Req-Line = "POST" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-GetActionRequest-URI-End

DSC-GetActionRequest-URI-End = "Action(ConfigurationId=" SQUOTE CONFIGURATIONID SQUOTE
                                RBRACKET FSLASH "GetAction"
                                SQUOTE = %x27 ; ' (Single Quote)
                                RBRACKET = %29 ; ) (Closing Bracket)
                                FSLASH = %2F ; / (Forward Slash)
                                CONFIGURATIONID = UUID ; as specified in [RFC4122]

DSC-GetActionSetReq-Headers = *( DSC-GetActionSetReq-Header-REQ
                                  / DSC-GetActionSetReq-Header-OPT )

DSC-GetActionSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
                                  / Accept ; section 14.1 of [RFC2616]
                                  / ContentType ' section 2.2.2.1.2
                                  / Content-Length ; section 14.13 of [RFC2616]

DSC-GetActionSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
                                  / Expect ; section 14.20 of [RFC2616]

DSC-GetActionReq-Body = ActionRequest ; section 3.3.5.1.1.1

```

The syntax of the GetAction response is defined as follows:

```

DSC-GetAction-Response = Status-Line
DSC-GetActionResp-Headers
DSC-GetActionResp-Body

DSC-GetActionResp-Headers = *( DSC-GetActionResp-Header-REQ
                                / DSC-GetActionResp-Header-OPT)

DSC-GetActionResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
                                / Content-Type ; section 2.2.2.1.2

DSC-GetActionResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-GetActionResp-Body = ActionContent ; section 3.3.5.1.1.2

```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.3.5.1.1.1 Request Body

The ActionRequest packet is used by the client to transfer the following data fields:

Checksum: A checksum as specified in section 2.2.2.2.

ChecksumAlgorithm: The algorithm for the Checksum as specified in section 2.2.2.3.

NodeCompliant: A value indicating TRUE or FALSE.

StatusCode: A value indicating a number between -2147483648 and 2147483647.

ConfigurationName: An opaque name as specified in section 2.2.2.4.

3.3.5.1.1.2 Response Body

The ActionContent packet is used by the server to transfer the following data field:

Value: MUST be either GetConfiguration, Retry<7>, or OK.

3.3.5.1.1.3 Processing Details

The client sends the GetAction request with content-type as application/json to the server with a request body as specified in section 3.3.5.1.1.1. The client MUST include **Checksum** and **ChecksumAlgorithm** in the request body. The client SHOULD include **StatusCode** in the request body. The server responds back with content-type as application/json with response body as specified in section 3.3.5.1.1.2.

3.3.6 Timer Events

None.

3.3.7 Other Local Events

None.

3.4 SendStatusReport Versions 1.0 and 1.1 Details

The SendStatusReport request SHOULD<8> send the status report, as specified in section 3.4.5.1.1.1, to the server. The SendStatusReport request maps to the HTTP POST request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.4.1 Abstract Data Model

None.

3.4.2 Timers

None.

3.4.3 Initialization

None.

3.4.4 Higher-Layer Triggered Events

None.

3.4.5 Message Processing Events and Sequencing Rules

Resource	Description
Node(ConfigurationID={ConfigurationId})/SendStatusReport	Send the status report to the server.

The response to all the methods results in one of the following status codes.

Status code	Reason phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The server could not read the request due to malformed syntax.
404	NOT FOUND	The resource is not found.

3.4.5.1 Node(ConfigurationID={ConfigurationId})/SendStatusReport

The following HTTP method can be performed on this resource.

HTTP method	Description
POST	Posts the data to the server and gets status from the server.

3.4.5.1.1 POST

The URL specified by the client in the HTTP request line of the POST request identifies the status point targeted for the client. The server can have multiple status points that have different access permissions associated with them. For example, some status points require HTTP access authentication (as specified in [RFC2616] section 11). As another example, status points allow only clients that connect from a specific IP address.

The syntax of the SendStatusReport request is defined as follows.

```
DSC-SendStatusReport-Request = DSC-SendStatusReport-Req-Line
                               DSC-SendStatusReportSetReq-Headers
                               DSC-SendStatusReportReq-Body

DSC-SendStatusReport-Req-Line = "POST" SP Request-URI SP HTTP-Version CRLF
```

```

Request-URI = Request-URI-Start DSC-SendStatusReportRequest-URI-End

DSC-SendStatusReportRequest-URI-End = "Nodes(ConfigurationId=" SQUOTE CONFIGURATIONID SQUOTE

RBRACKET FSLASH "SendStatusReport"
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
ConfigurationID = UUID ; as specified in [RFC4122]

DSC-SendStatusReportSetReq-Headers = *( DSC-SendStatusReportSetReq-Header-REQ
    / DSC-SendStatusReportSetReq-Header-OPT )

DSC-SendStatusReportSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
    / Accept ; section 14.1 of [RFC2616]
    / ContentType ' section 2.2.2.1.2
    / Content-Length ; section 14.13 of [RFC2616]

DSC-SendStatusReportSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
    / Expect ; section 14.20 of [RFC2616]

DSC-SendStatusReportReq-Body = StatusReportRequest ; section 3.4.5.1.1.1

```

The syntax of the SendStatusReport response is defined as follows:

```

DSC-SendStatusReport-Response = Status-Line
DSC-SendStatusReportResp-Headers
DSC-SendStatusReportResp-Body

DSC-SendStatusReportResp-Headers = *( DSC-SendStatusReportResp-Header-REQ
    / DSC-SendStatusReportResp-Header-OPT)

DSC-SendStatusReportResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
    / Content-Type ; section 2.2.2.1.2

DSC-SendStatusReportResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-SendStatusReportResp-Body = StatusReportContent ; section 3.4.5.1.1.2

```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.4.5.1.1.1 Request Body

The StatusReportRequest packet is used by the client to transfer the following data fields:

JobId: The JobId parameter is a universally unique identifier (UUID) as specified in [RFC4122] section 3.

NodeName: A value that is used to identify the name of the client.

OperationType: A string value that identifies the type for the operation.

LCMVersion: A value that contains a string of two to four groups of digits where the groups are separated by a period that identifies the report generator on the client.

ReportFormatVersion: A value that contains a string of two to four groups of digits where the groups are separated by a period that finds the identifier for the report.

ConfigurationVersion: A value that contains a string of two to four groups of digits where the groups are separated by a period.

IpAddress: A value that identifies the IP addresses of the client separated by a semicolon (;).

StartTime: A value that identifies the start time of an operation on the client.

EndTime: A value that identifies the end time of an operation on the client.

Errors: A set of string values that represents the errors for an operation on the client.

StatusData: A set of string values that represents the status of an operation on the client.

3.4.5.1.1.2 Response Body

The StatusReportContent packet does not contain any data.

3.4.5.1.1.3 Processing Details

The client sends the SendStatusReport request with content-type as application/json to the server with a request body as specified in section 3.4.5.1.1.1. The client MUST include JobId in the request body. The server responds back with status codes as specified in section 3.4.5.1.1.

3.4.6 Timer Events

None.

3.4.7 Other Local Events

None.

3.5 GetStatusReport Versions 1.0 and 1.1 Details

The GetStatusReport request SHOULD get the status report from the server, as specified in section 3.5.5.1.1. The GetStatusReport request maps to the HTTP GET request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.5.1 Abstract Data Model

None.

3.5.2 Timers

None.

3.5.3 Initialization

None.

3.5.4 Higher-Layer Triggered Events

None.

3.5.5 Message Processing Events and Sequencing Rules

Resource	Description
Node(ConfigurationId={ConfigurationId})/Reports(JobId={JobId}))	Get the status report from the server.

The responses to all the methods can result in the following status codes.

Status Code	Reason Phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
404	NOT FOUND	The resource is not found.

3.5.5.1 Node(ConfigurationId={ConfigurationId})/StatusReports

The following HTTP method can be performed on this resource.

HTTP Method	Description
GET	Gets the status report from the server.

3.5.5.1.1 GET

The URL specified by the client in the HTTP request line of the GET request identifies the "status point" targeted for the client. The server might have multiple status points and different status points might have different access permissions associated with them. For example, some status points require HTTP access authentication (as specified in [RFC2616] section 11). Other status points allow only clients that connect from a specific IP address.

The syntax of the GetStatusReport request is defined as follows.

```
DSC-GetStatusReport-Request = DSC-GetStatusReport-Req-Line
                             DSC-GetStatusReportSetReq-Headers

DSC-GetStatusReport-Req-Line = "GET" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-GetStatusReportRequest-URI-End

DSC-GetStatusReportRequest-URI-End = "Node (ConfigurationId=" SQUOTE CONFIGURATIONID SQUOTE
RBRACKET FSLASH "Reports(JobId=" SQUOTE JOBID SQUOTE
RBRACKET
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
ConfigurationID = UUID ; as specified in [RFC4122]
JOBID = UUID; as specified in [RFC4122]

DSC-GetStatusReportSetReq-Headers = *( DSC-GetStatusReportSetReq-Header-REQ
```

```

/ DSC-GetStatusReportSetReq-Header-OPT )

DSC-GetStatusReportSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
/ Accept ; section 14.1 of [RFC2616]
/ ContentType ' section 2.2.2.1.2
/ Content-Length ; section 14.13 of [RFC2616]

DSC-GetStatusReportSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
/ Expect ; section 14.20 of [RFC2616]

```

The syntax of the GetStatusReport response is defined as follows:

```

DSC-GetStatusReport-Response = Status-Line
DSC-GetStatusReportResp-Headers
DSC-GetStatusReportResp-Body

DSC-GetStatusReportResp-Headers = *( DSC-GetStatusReportResp-Header-REQ
/ DSC-GetStatusReportResp-Header-OPT)

DSC-GetStatusReportResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
/ Content-Type ; section 2.2.2.1.2

DSC-GetStatusReportResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-GetStatusReportResp-Body = StatusReportContent ; section 3.4.5.1.1.2

```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.5.5.1.1.1 Request Body

There is no information transferred in the request body.

3.5.5.1.1.2 Response Body

StatusReportContent represents a BLOB.

3.5.5.1.1.3 Processing Details

The client sends the GetStatusReport request with the content-type as application/json to the server with a request body as specified in section 3.5.5.1.1.1. The server responds back with status codes as specified in section 3.5.5.1.1.

3.5.6 Timer Events

None.

3.5.7 Other Local Events

None.

3.6 GetConfiguration Version 2.0 Details

The GetConfiguration request SHOULD<10> get the configuration from the server. The GetConfiguration request maps to an HTTP GET request in which the Content-Type header is an application/octet-stream.

3.6.1 Abstract Data Model

The server MUST maintain a ConfigurationTable where each entry contains:

ServerAgentId: A unique combination of an AgentId (section 2.2.3.4) and a ConfigurationName (section 2.2.2.4). The AgentId MUST NOT be empty.

ServerConfigurationData: A BLOB that is not interpreted as part of this protocol and is passed on to higher layers as is.

3.6.2 Timers

None.

3.6.3 Initialization

None.

3.6.4 Higher-Layer Triggered Events

None.

3.6.5 Message Processing Events and Sequencing Rules

The server MUST match the AgentId (section 2.2.3.4) from the URL and, if specified, the ConfigurationName (section 2.2.2.4) from the headers with the ServerAgentId in the ConfigurationTable. The server MUST use case-insensitive ordinal comparison to match the AgentId and ConfigurationName. If a match is found, the server MUST return ServerConfigurationData to the client with status code 200. If a match is not found, the server MUST return status code 404.

Resource	Description
Nodes(AgentId={AgentId})/ Configurations(ConfigurationName={ConfigurationName})/ConfigurationContent	Gets the configuration from the server.

Request header	Usage	Value
ProtocolVersion	Required	Specified in section 2.2.2.5.

The responses to all the methods can result in the following status codes.

Status code	Reason phrase	Description
200	OK	Returned when the request is completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.

Status code	Reason phrase	Description
401	UNAUTHORIZED	The client is not authorized.
404	NOT FOUND	Returned when the resource is not found.

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
checksum	Required	Specified in section 2.2.2.2.
checksumalgorithm	Required	See section 2.2.2.3.
configurationname	Optional	See section 2.2.2.4.
protocolversion	Required	See section 2.2.2.5.

3.6.5.1 Nodes(**AgentId**=**{AgentId}**)/ Configurations(**ConfigurationName**=**{ConfigurationName}**)/**ConfigurationContent**

The following HTTP method is allowed to be performed on this resource.

HTTP method	Description
GET	Gets the configuration from the server.

3.6.5.2 GET

The URL specified by the client in the HTTP request line of the GET request identifies a "configuration point" targeted for the client. The server can have multiple configuration points and different configuration points can have different access permissions associated with them. For example, some configuration points require HTTP access authentication (as specified in [RFC2616] section 11). Or, a configuration point could allow only clients that connect from a specific IP address.

The syntax of the GetConfiguration request is defined as follows.

```

DSC-GetConfiguration-Request    = DSC-GetConfiguration-Req-Line
                                DSC-GetConfigurationSetReq-Headers

DSC-GetConfiguration-Req-Line  = "GET" SP Request-URI SP HTTP-Version CRLF

Request-URI = Request-URI-Start DSC-GetConfigurationRequest-URI-End

DSC-GetConfigurationSetReq-Headers = *( DSC-GetConfigurationSetReq-Header-REQ
    / DSC-GetConfigurationSetReq-Header-OPT )

DSC-GetConfigurationSetReq-Header-REQ    = Host      ; section 14.23 of [RFC2616]

DSC-GetConfigurationSetReq-Header-OPT    = Connection ; section 14.10 of [RFC2616]
    / ConfigurationName ; section 2.2.2.4

DSC-GetConfigurationRequest-URI-End = "Nodes(AgentId=" SQUOTE AGENTID SQUOTE RBRACKET
    FSLASH (ConfigurationName=" SQUOTE CONFIGURATIONNAME SQUOTE

```

```

RBRACKET FSLASH "ConfigurationContent"
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
AGENTID = UUID ; as specified in [RFC4122]
CONFIGURATIONNAME as defined in 2.2.2.4

```

The syntax of the GetConfiguration response is defined as follows:

```

DSC-GetConfiguration-Response = Status-Line
DSC-GetConfigurationResp-Headers
DSC-GetConfigurationResp-Body

DSC-GetConfigurationResp-Headers = *( DSC-GetConfigurationResp-Header-REQ
                                        / DSC-GetConfigurationResp-Header-OPT
                                        / DSC-GetConfigurationResp-Body)

DSC-GetConfigurationResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
                                        / Content-Type ; section 2.2.2.1.1
                                        / Checksum ; section 2.2.2.2
                                        / ChecksumAlgorithm ; section 2.2.2.3

DSC-GetConfigurationResp-Header-OPT = Server ; section 14.38 of [RFC2616]

DSC-GetConfigurationResp-Body = Configuration ; section 3.6.5.2.2

```

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
Checksum	Required	See section 2.2.2.2.
ChecksumAlgorithm	Required	See section 2.2.2.3.
ProtocolVersion	Required	See section 2.2.2.5

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
401	Not authorized.
404	The resource is not found.

3.6.5.2.1 Request Body

None.

3.6.5.2.2 Response Body

In the response body, the configuration represents a BLOB.

3.6.5.2.3 Processing Details

The client gets the configuration from the server as content-type application/octet-stream in the response body for the GetConfiguration request. The server MUST send the checksum in the response headers as specified in section 2.2.2.2. The server MUST send the ChecksumAlgorithm in the response headers as specified in section 2.2.2.3. The server MUST send the ProtocolVersion in the response headers as specified in section 2.2.2.5. The server generates the checksum using the following algorithm:

- Use the algorithm specified in section 2.2.2.3 to compute the hash of the response body as specified in [RFC4634] section 4.1.
- Perform base16 encoding of the computed hash as specified in [RFC4648] section 8.

3.6.6 Timer Events

None.

3.6.7 Other Local Events

None.

3.7 GetModule Version 2.0 Details

The GetModule request SHOULD<11> get the module from the server. The GetModule request maps to the HTTP GET request with the content-type as application/octet-stream as part of the request.

3.7.1 Abstract Data Model

The server MUST maintain a ModuleTable in which each entry contains the following:

ServerAgentId: The AgentId (section 2.2.2.6).

ServerModuleName: The ModuleName (section 2.2.3.2).

ServerModuleVersion: The ModuleVersion (section 2.2.3.3).

ServerModuleData: A BLOB of data. This data is not interpreted as part of this protocol and is passed on to higher layers as is.

3.7.2 Timers

None.

3.7.3 Initialization

None.

3.7.4 Higher-Layer Triggered Events

None.

3.7.5 Message Processing Events and Sequencing Rules

The server MUST match ModuleName with ServerModuleName, and ModuleVersion with the ServerModuleVersion of the ModuleTable. The server MUST use case-insensitive ordinal comparison to match ModuleName and ModuleVersion. For a ServerAgentId, the server MUST have a unique combination of ServerModuleName and ServerModuleVersion. ServerModuleName in the ModuleTable

MUST NOT be empty. If a match is found, the server returns ModuleData to the client with status code 200. If a match is not found, the server returns status code 404.

Resource	Description
Modules(ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent	Get the module from the server.

Responses to the methods can result in one of the following status codes.

Status code	Reason phrase	Description
200	OK	Request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
401	NOT AUTHORIZED	The client is not authorized.
404	NOT FOUND	Used in cases where the resource is not found.

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
AgentId	Required	See section 2.2.2.6.
checksum	Required	See section 2.2.2.2.
checksumalgorithm	Required	See section 2.2.2.3.
protocolversion	Required	See section 2.2.2.5.

3.7.5.1 Modules(ModuleName={moduleName},ModuleVersion={moduleVersion})/ModuleContent

The following HTTP method can be performed on this resource.

HTTP method	Description
GET	Gets the module from the server.

3.7.5.1.1 GET

The URL specified by the client in the HTTP request line of the GET request identifies a "module point" targeted for the client. The server might have multiple module points and different module points can have different access permissions associated with them. For example, some module points require HTTP access authentication (as specified in [RFC2616] section 11). Other module points allow only clients that connect from a specific IP address.

The syntax of the GetModule request is as follows.


```

DSC-GetModule-Request      = DSC-GetModule-Req-Line
                             DSC-GetModuleSetReq-Headers

DSC-GetModule-Req-Line    = "GET" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-GetModuleRequest-URI-End
DSC-GetModuleSetReq-Headers = *( DSC-GetModuleSetReq-Header-REQ
    / DSC-GetModuleSetReq-Header-OPT )

DSC-GetModuleSetReq-Header-REQ    = Host      ; section 14.23 of [RFC2616]

DSC-GetModuleSetReq-Header-OPT    = Connection ; section 14.10 of [RFC2616]
DSC-GetModuleRequest-URI-End = "Modules(ModuleName=" SQUOTE MODULENAME SQUOTE
    ",ModuleVersion=" SQUOTE MODULEVERSION SQUOTE
    RBRACKET FSLASH "ModuleContent"

SQUOTE = %x27 ; ' (Single Quote)
MODULENAME = ModuleName; as specified in section 2.2.3.3
MODULEVERSION = *(DIGIT)[ 0x2E *(DIGIT)]
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)

```

The syntax of the GetModule response is as follows:

```

DSC-GetModule-Response = Status-Line
                        DSC-GetModuleResp-Headers
                        DSC-GetModuleResp-Body

DSC-GetModuleResp-Headers = *( DSC-GetModuleResp-Header-REQ
    / DSC-GetModuleResp-Header-OPT)

DSC-GetModuleResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
    / Content-Type ; section 2.2.2.1.1
    / Checksum ; section 2.2.2.2
    / ChecksumAlgorithm ; section 2.2.2.3

DSC-GetModuleResp-Header-OPT = Server      ; section 14.38 of [RFC2616]
DSC-GetModuleResp-Body = ModuleData ; section 3.2.2.5.1.1.2

```

The response message for this operation contains the following HTTP headers.

Response header	Usage	Value
checksum	Required	See section 2.2.2.2.
ProtocolVersion	Required	See section 2.2.2.5.
ChecksumAlgorithm	Required	See section 2.2.2.3.

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
401	Not authorized.
404	The resource is not found.

3.7.5.1.1.1 Request Body

None.

3.7.5.1.1.2 Response Body

ModuleData represents a BLOB.

3.7.5.1.1.3 Processing Details

The client gets the module from the server as content-type application/octet-stream in the response body for the GetModule request. The server MUST send the checksum in response headers as specified in section 2.2.2.2. The server MUST send the ChecksumAlgorithm in the response headers as specified in section 2.2.2.3. The server MUST send the ProtocolVersion in the response headers as specified in section 2.2.2.5. The server generates the checksum using the following algorithm:

- Use the algorithm specified in ChecksumAlgorithm to compute the hash of the response body as specified in [RFC4634] section 4.1.
- Perform base16 encoding of the computed hash as specified in [RFC4648] in section 8.

3.7.6 Timer Events

None.

3.7.7 Other Local Events

None.

3.8 GetDscAction Version 2.0 Details

The GetDscAction request SHOULD<12> get the action, as specified in section 3.8.5.1.1.2, from the server. The GetDscAction request maps to HTTP POST request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.8.1 Abstract Data Model

None.

3.8.2 Timers

None.

3.8.3 Initialization

None.

3.8.4 Higher-Layer Triggered Events

None.

3.8.5 Message Processing Events and Sequencing Rules

Resource	Description
Nodes(AgentId={AgentId})/GetDscAction	Get the action from the server.

The responses to all the methods can result in the following status codes.

Status code	Reason phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
401	UNAUTHORIZED	The client is not authorized to send the request.
404	NOT FOUND	The resource is not found.

3.8.5.1 Nodes(AgentId={AgentId})/GetDscAction

The following HTTP method is allowed to be performed on this resource.

HTTP method	Description
POST	POSTs the data to the server and gets action from the server.

3.8.5.1.1 POST

The URL specified by the client in the HTTP request line of the POST request identifies the action point targeted for the client. The server can have multiple action points and different action points can have different access permissions associated with them. For example, some action points require HTTP access authentication (as specified in [RFC2616] section 11). Or, action points can also allow only clients that connect from a specific IP address.

The syntax of the GetDscAction request is defined as follows.

```

DSC-GetDscAction-Request = DSC-GetDscAction-Req-Line
                          DSC-GetDscActionSetReq-Headers
                          DSC-GetDscActionReq-Body

DSC-GetDscAction-Req-Line = "POST" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-GetDscActionRequest-URI-End

DSC-GetDscActionRequest-URI-End = "Nodes(AgentId=" SQUOTE AGENTID SQUOTE
RBRACKET FSLASH "GetDscAction"
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
AGENTID = UUID ; as specified in [RFC4122]

DSC-GetDscActionSetReq-Headers = *( DSC-GetDscActionSetReq-Header-REQ
/ DSC-GetDscActionSetReq-Header-OPT )

DSC-GetDscActionSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
/ Accept ; section 14.1 of [RFC2616]
/ ContentType ' section 2.2.2.1.2

```

```

    / Content-Length ; section 14.13 of [RFC2616]

DSC-GetDscActionSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
    / Expect ; section 14.20 of [RFC2616]

DSC-GetDscActionReq-Body = ActionRequest ; section 3.8.5.1.1.1

```

The syntax of the GetDscAction response is defined as follows:

```

DSC-GetDscAction-Response = Status-Line
DSC-GetDscActionResp-Headers
DSC-GetDscActionResp-Body

DSC-GetDscActionResp-Headers = *( DSC-GetDscActionResp-Header-REQ
    / DSC-GetDscActionResp-Header-OPT)

DSC-GetDscActionResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
    / Content-Type ; section 2.2.2.1.2

DSC-GetDscActionResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-GetDscActionResp-Body = ActionContent ; section 3.8.5.1.1.2

```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
401	Unauthorized.
404	The resource is not found.

3.8.5.1.1.1 Request Body

The ActionRequest packet is used by the client to transfer the following data fields:

ClientStatus: An array of the following fields:

Checksum: A checksum as specified in section 2.2.2.2.

ChecksumAlgorithm: The algorithm for the Checksum as specified in section 2.2.2.3.

ConfigurationName: An opaque name as specified in section 2.2.2.4.

3.8.5.1.1.2 Response Body

The ActionContent packet is used by the server to transfer the following data fields:

NodeStatus: MUST be either GetConfiguration, UpdateMetaConfiguration, Retry, or OK.

Details: An array of the following fields:

ConfigurationName: An opaque name as specified in section 2.2.2.4.

Status: MUST be either GetConfiguration, UpdateMetaConfiguration, Retry, or OK.

3.8.5.1.1.3 Processing Details

The client sends the GetDscAction request with content-type as application/json to the server with a request body as specified in section 3.8.5.1.1.1. The client MAY include ClientStatus in the request body. The server responds back with content-type as application/json with response body as specified in section 3.8.5.1.1.2.

3.8.6 Timer Events

None.

3.8.7 Other Local Events

None.

3.9 RegisterDscAgent Version 2 Details

The RegisterDscAgent request SHOULD<13> register a client with a server, as specified in section 3.9.5.1.1.1. The RegisterDscAgent request maps to the HTTP PUT request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.9.1 Abstract Data Model

None.

3.9.2 Timers

None.

3.9.3 Initialization

None.

3.9.4 Higher-Layer Triggered Events

None.

3.9.5 Message Processing Events and Sequencing Rules

Resource	Description
Nodes(AgentId={AgentId})	Register a client.

The responses to all the methods can result in the following status codes:

Status Code	Reason Phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
404	NOT FOUND	The resource is not found.

3.9.5.1 Nodes(**AgentId**=**{AgentId}**)

The following HTTP method can be performed on this resource:

HTTP Method	Description
PUT	Sends the registration to the server.

3.9.5.1.1 PUT

The URL specified by the client in the HTTP request line of the PUT request identifies the "registration point" targeted for the client. The server might have multiple registration points and different registration points might have different access permissions associated with them. For example, some registration points require HTTP access authentication (as specified in [RFC2616] section 11). Other registration points allow only clients that connect from a specific IP address.

The syntax of the RegisterDscAgent request is defined as follows:

```
DSC-RegisterDscAgent-Request = DSC-RegisterDscAgent-Req-Line
                               DSC-RegisterDscAgentReq-Headers

DSC-RegisterDscAgent-Req-Line = "PUT" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-RegisterDscAgent-URI-End

DSC- RegisterDscAgentRequest-URI-End = "Nodes (Agentid=" SQUOTE AGENTID SQUOTE
RBRACKET
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
AgentID = UUID ; as specified in [RFC4122]

DSC-RegisterDscAgentReq-Headers = *( DSC-RegisterDscAgentSetReq-Header-REQ
   / DSC-RegisterDscAgentSetReq-Header-OPT )

DSC- RegisterDscAgentSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
   / Accept ; section 14.1 of [RFC2616]
   / ContentType ' section 2.2.2.1.2
   / Content-Length ; section 14.13 of [RFC2616]

DSC- RegisterDscAgent SetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
   / Expect ; section 14.20 of [RFC2616]

DSC-RegisterDscAgentReq-Body = RegisterDscAgentRequest ; section 3.9.5.1.1.1
```

The syntax of the RegisterDscAgent response is defined as follows:

```
DSC-RegisterDscAgent-Response = Status-Line
DSC-RegisterDscAgentResp-Headers
DSC-RegisterDscAgentResp-Body

DSC-RegisterDscAgentResp-Headers = *( DSC-RegisterDscAgentResp-Header-REQ
   / DSC-RegisterDscAgentResp-Header-OPT)

DSC-RegisterDscAgentResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
   / Content-Type ; section 2.2.2.1.2

DSC-RegisterDscAgentResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-RegisterDscAgentResp-Body = RegisterDscAgentContent; section 3.9.5.1.1.2
```

The response message for this method can result in the following status codes:

Status code	Description
200	Request completed.
400	Bad request.
404	The resource is not found.

3.9.5.1.1.1 Request Body

The RegisterDscAgentRequest packet is used by the client to transfer the following data fields:

NodeName: A value that identifies the name of the client.

LCMVersion: A value that identifies the report generator on the client.

ConfigurationNames: A set of values that define the configurations that MAY be targeted to this client.

IpAddress: A value that identifies the IP addresses of the client separated by a semicolon (;).

AgentInformation: A set of values describing the agent including LCMVersion, NodeName, and IpAddress.

CertificateInformation: A set of values describing the certificate generated on the client used for client validation, including ~~Certificate-FriendlyName~~, ~~Certificate-Issuer~~, ~~Certificate-NotAfter~~, ~~Certificate-NotBefore~~, ~~Certificate-Subject~~, ~~Certificate-PublicKey~~, ~~Certificate-Thumbprint~~, and ~~Certificate~~ Version.

PublicKey: This value describes the certificate generated on the client. The value is in format base64 encoded raw bytes of the certificate's public key followed by ';' followed by the OID of the public key's hash algorithm.<14>

3.9.5.1.1.2 Response Body

RegisterDscAgentContent represents a BLOB.

3.9.5.1.1.3 Processing Details

The client sends the RegisterDscAgent request with the content-type as application/json to the server with a request body as specified in section 3.9.5.1.1.1. The server responds back with status codes as specified in section 3.9.5.1.1.

3.9.6 Timer Events

None.

3.9.7 Other Local Events

None.

3.10 SendReport Version 2.0 Details

The SendReport request SHOULD send the status report, as specified in section 3.10.5.1.1.1, to the server. The SendReport request maps to the HTTP POST request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.10.1 Abstract Data Model

None.

3.10.2 Timers

None.

3.10.3 Initialization

None.

3.10.4 Higher-Layer Triggered Events

None.

3.10.5 Message Processing Events and Sequencing Rules

Resource	Description
Nodes(AgentID={AgentId})/SendReport	Send the status report to the server.

The response to all the methods results in one of the following status codes.

Status code	Reason phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The server could not read the request due to malformed syntax.
401	UNAUTHORIZED	The client is not authorized to send a report.
404	NOT FOUND	The resource is not found.

3.10.5.1 Nodes(AgentID={AgentId})/SendReport

The following HTTP method can be performed on this resource.

HTTP method	Description
POST	Posts the data to the server and gets status from the server.

3.10.5.1.1 POST

The URL specified by the client in the HTTP request line of the POST request identifies the status point targeted for the client. The server can have multiple status points that have different access permissions associated with them. For example, some status points require HTTP access authentication (as specified in [RFC2616] section 11). Other status points allow only clients that connect from a specific IP address.

The syntax of the SendReport request is defined as follows.

```

DSC-SendReport-Request = DSC-SendReport-Req-Line
                        DSC-SendReportSetReq-Headers
                        DSC-SendReportReq-Body

DSC-SendReport-Req-Line = "POST" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-SendReportRequest-URI-End

DSC-SendReportRequest-URI-End = "Node (AgentId=" SQUOTE AGENTID SQUOTE

RBRACKET FSLASH "SendReport"
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
AgentID = UUID ; as specified in [RFC4122]

DSC-SendReportSetReq-Headers = *( DSC-SendReportSetReq-Header-REQ
/ DSC-SendReportSetReq-Header-OPT )

DSC-SendReportSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
/ Accept ; section 14.1 of [RFC2616]
/ ContentType ' section 2.2.2.1.2
/ Content-Length ; section 14.13 of [RFC2616]

DSC-SendReportSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
/ Expect ; section 14.20 of [RFC2616]

DSC-SendReportReq-Body = ReportRequest ; section 3.10.5.1.1.1

```

The syntax of the SendReport response is defined as follows:

```

DSC-SendReport-Response = Status-Line
DSC-SendReportResp-Headers
DSC-SendReportResp-Body

DSC-SendReportResp-Headers = *( DSC-SendReportResp-Header-REQ
/ DSC-SendReportResp-Header-OPT)

DSC-SendReportResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
/ Content-Type ; section 2.2.2.1.2

DSC-SendReportResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-SendReportResp-Body = ReportContent ; section 3.10.5.1.1.2

```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
401	Unauthorized.
404	The resource is not found.

3.10.5.1.1.1 Request Body

The ReportRequest packet is used by the client to transfer the following data fields:

JobId: The JobId parameter is a universally unique identifier (UUID) as specified in [RFC4122] section 3.

OperationType: A value that identifies the type for the operation.

RefreshMode: A value that identifies whether the client is in PUSH or PULL mode.

Status: A value that identifies the status of the current operation.

LCMVersion: A value that identifies the report generator on the client.

ReportFormatVersion: A value that finds the identifier for the report.

ConfigurationVersion: A value that contains a string of two to four groups of digits where the groups are separated by a period.

NodeName: A value that is used to identify the name of the client.

IpAddress: A value that identifies the IP addresses of the client separated by a semicolon (;).

StartTime: A value that identifies the start time of an operation on the client.

EndTime: A value that identifies the end time of an operation on the client.

RebootRequested: A value that identifies whether the client requested a reboot.

Errors: A value that represents the errors for an operation on the client.

StatusData: A value that represents the status of an operation on the client.

AdditionalData: An array of key value pairs that represents additional data that the client is sending to the report server.

3.10.5.1.1.2 Response Body

The ReportContent packet does not contain any data.

3.10.5.1.1.3 Processing Details

The client sends the SendReport request with content-type as application/json to the server with a request body as specified in section 3.10.5.1.1.1. The client MUST include JobId in the request body. The server responds back with status codes as specified in section 3.10.5.1.1.

3.10.6 Timer Events

None.

3.10.7 Other Local Events

None.

3.11 GetReports Version 2.0 Details

The GetReports request SHOULD get the status report from the server, as specified in section 3.11.5.1.1.1. The GetReports request maps to the HTTP GET request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

3.11.1 Abstract Data Model

None.

3.11.2 Timers

None.

3.11.3 Initialization

None.

3.11.4 Higher-Layer Triggered Events

None.

3.11.5 Message Processing Events and Sequencing Rules

Resource	Description
Nodes(AgentId={AgentId})/Reports(JobId={JobId}))	Get the report from the server.

The responses to all the methods can result in the following status codes.

Status Code	Reason Phrase	Description
200	OK	The request completed.
400	BAD REQUEST	The request could not be understood by the server due to malformed syntax.
401	NOT AUTHORIZED	The client is not authorized to send the request.
404	NOT FOUND	The resource is not found.

3.11.5.1 Nodes(AgentId={AgentId})/Reports

The following HTTP method can be performed on this resource.

HTTP Method	Description
GET	Gets the report from the server.

3.11.5.1.1 GET

The URL specified by the client in the HTTP request line of the GET request identifies the "reporting point" targeted for the client. The server might have multiple reporting points and different reporting points might have different access permissions associated with them. For example, some reporting points require HTTP access authentication (as specified in [RFC2616] section 11). Other reporting points allow only clients that connect from a specific IP address.

The syntax of the GetReports request is defined as follows.

```
DSC-GetReports-Request = DSC- GetReports -Req-Line
                        DSC- GetReportsSetReq-Headers
DSC-GetReports-Req-Line = "GET" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-GetReportsRequest-URI-End

DSC-GetReportsRequest-URI-End = "Nodes (AgentId=" SQUOTE AGENTID SQUOTE

RBRACKET FSLASH "Reports(JobId=" SQUOTE JOBID SQUOTE
RBRACKET
SQUOTE = %x27 ; ' (Single Quote)
RBRACKET = %29 ; ) (Closing Bracket)
FSLASH = %2F ; / (Forward Slash)
AgentID = UUID ; as specified in [RFC4122]
JOBID = UUID; as specified in [RFC4122]

DSC-GetReportsSetReq-Headers = *( DSC-GetReportsSetReq-Header-REQ
/ DSC-GetReportsSetReq-Header-OPT )

DSC-GetReportsSetReq-Header-REQ = Host ; section 14.23 of [RFC2616]
/ Accept ; section 14.1 of [RFC2616]
/ ContentType ' section 2.2.2.1.2
/ Content-Length ; section 14.13 of [RFC2616]

DSC-GetReportsSetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
/ Expect ; section 14.20 of [RFC2616]
```

The syntax of the GetReports response is defined as follows:

```
DSC-GetReports-Response = Status-Line
DSC-GetReportsResp-Headers
DSC-GetReportsResp-Body

DSC-GetReportsResp-Headers = *( DSC-GetReportsResp-Header-REQ
/ DSC-GetReportsResp-Header-OPT)

DSC-GetReportsResp-Header-REQ = Content-Length ; section 14.13 of [RFC2616]
/ Content-Type ; section 2.2.2.1.2

DSC-GetReportsResp-Header-OPT = Server ; section 14.38 of [RFC2616]
DSC-GetReportsResp-Body = ReportContent ; section 3.11.5.1.1.2
```

The response message for this method can result in the following status codes.

Status code	Description
200	Request completed.
400	Bad request.
401	Not authorized.
404	The resource is not found.

3.11.5.1.1.1 Request Body

There is no information transferred in the request body.

3.11.5.1.1.2 Response Body

ReportsContent represents a BLOB.

3.11.5.1.1.3 Processing Details

The client sends the GetReports request with the content-type as application/json to the server with a request body as specified in section 3.11.5.1.1.1. The server responds back with status codes as specified in section 3.11.5.1.1.2.

3.11.6 Timer Events

None.

3.11.7 Other Local Events

None.

3.12 CertificateRotation Details

With the CertificateRotation request, the server MUST rotate the client certificate with the new certificate as specified in section 3.2.5.1.1.1.<17> The CertificateRotation request maps to the HTTP POST request with content-type as application/json, as specified in Appendix A: Full JSON Schema (section 6), as part of the request.

The server MAY reject the CertificateRotation request if server has not sent a DSC-CertificateRotation response header in any of the previous responses (section 2.2.2.8).

3.12.1 Abstract Data Model

None.

3.12.2 Timers

None.

3.12.3 Initialization

None.

3.12.4 Higher-Layer Triggered Events

None.

3.12.5 Message Processing Events and Sequencing Rules

<u>Resource</u>	<u>Description</u>
Nodes(AgentId={AgentId})/CertificateRotation	Rotate the client certificate to a new certificate as specified in the request.

The responses to all the methods can result in the following status codes:

<u>Status Code</u>	<u>Reason Phrase</u>	<u>Description</u>
201	Created	The rotation request was created.
409	Conflict	Certificate rotation is already in progress.
404	NOT FOUND	The resource is not found.

3.12.5.1 Nodes(AgentId={AgentId})/CertificateRotation

The following HTTP method can be performed on this resource:

<u>HTTP Method</u>	<u>Description</u>
POST	Rotate the client certificate to a new certificate as specified in the request.

3.12.5.1.1 POST

The URL specified by the client in the HTTP request line of the POST request identifies the "certificate rotation point" targeted for the client.

The syntax of the CertificateRotation request is defined as follows.

```

DSC-CertificateRotation-Request = DSC-CertificateRotation-Req-Line
                                DSC-CertificateRotationSetReq-Headers

DSC-CertificateRotation-Req-Line = "POST" SP Request-URI SP HTTP-Version CRLF
Request-URI = Request-URI-Start DSC-CertificateRotation-URI-End

DSC-CertificateRotation-URI-End = "Nodes(Agentid=" SQUOTE AGENTID SQUOTE
                                RBRACKET FSLASH "CertificateRotation"
                                SQUOTE = %x27 ; ' (Single Quote)
                                RBRACKET = %29 ; ) (Closing Bracket)
                                FSLASH = %2F ; / (Forward Slash)
                                AgentID = UUID ; as specified in [RFC4122]

DSC-CertificateRotation-Headers = *( DSC-CertificateRotationSetReq-Header-REQ
                                     / DSC-CertificateRotationSetReq-Header-OPT )

DSC-CertificateRotation-Header-REQ = Host ; section 14.23 of [RFC2616]
                                   / Accept ; section 14.1 of [RFC2616]
                                   / ContentType ' section 2.2.2.1.2
                                   / Content-Length ; section 14.13 of [RFC2616]

DSC-CertificateRotation SetReq-Header-OPT = Connection ; section 14.10 of [RFC2616]
                                           / Expect ; section 14.20 of [RFC2616]

DSC-CertificateRotation-Body = CertificateRotationRequest ; section 3.12.5.1.1.1

```

The response message for this method can result in the following status codes:

Status code	Description
<u>201</u>	<u>Created</u>
<u>400</u>	<u>Bad request.</u>
<u>404</u>	<u>The resource is not found.</u>
<u>409</u>	<u>A conflict occurred.</u>

3.12.5.1.1.1 Request Body

The client transfers the following data fields in the body of the CertificateRotation request:

CertificateInformation: A set of values describing the certificate generated on the client used for client validation, including Certificate FriendlyName, Certificate Issuer, Certificate NotAfter, Certificate NotBefore, Certificate Subject, Certificate PublicKey, Certificate Thumbprint, and Certificate Version.

PublicKey: This value describes the certificate generated on the client. The value is in format base64 encoded raw bytes of the certificate's public key followed by `;` followed by OID of the public key's hash algorithm.

3.12.5.1.1.2 Response Body

None.

3.12.5.1.1.3 Processing Details

The client sends the CertificateRotation request with the content-type as application/json to the server with a request body as specified in section 3.11.5.1.1.1. The server responds back with status codes as specified in section 3.11.5.1.1.

3.12.6 Timer Events

None.

3.12.7 Other Local Events

None.

4 Protocol Examples

4.1 GetConfiguration Sequence

The following sequence occurs between a client and a server during a GetConfiguration request.

1. The client sends a GetConfiguration request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a "200 OK" HTTP response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single GetConfiguration request.




Figure 1: Message sequence for a single GetConfiguration request

4.2 GetModule Sequence

The following sequence occurs between a client and a server during a GetModule request.

1. The client sends a GetModule request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a "200 OK" HTTP response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single GetModule request.




Figure 2: Message sequence for a single GetModule request

4.3 GetAction Sequence

The following sequence occurs between a client and a server during a GetAction request.

- 1. The client sends a GetAction request.
- 2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
- 3. If authentication is not required, or if authentication has succeeded, the server responds with a "200 OK" HTTP response.
- 4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single GetAction request.




Figure 3: Message sequence with a single GetAction request

4.4 SendStatusReport Sequence

The following sequence occurs between a client and a server during a SendStatusReport request.

1. The client sends a SendStatusReport request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a HTTP 200 (OK) response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single SendStatusReport request.




Figure 4: Message sequence with a single SendStatusReport

4.5 GetStatusReport Sequence

The following sequence occurs between a client and a server during a GetStatusReport request.

1. The client sends a GetStatusReport request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a HTTP 200 (OK) response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single GetStatusReport request.




Figure 5: Message sequence with a single GetStatusReport

4.6 RegisterDscAgent Sequence

The following sequence occurs between a client and a server during a RegisterDscAgent request.

1. The client sends a RegisterDscAgent request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a HTTP 200 (OK) response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single RegisterDscAgent request.




Figure 6: Message sequence with a single RegisterDscAgent

4.7 SendReport Sequence

The following sequence occurs between a client and a server during a SendReport request.

1. The client sends a SendReport request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a HTTP 200 (OK) response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single SendReport request.




Figure 7: Message sequence with a single SendReport request

4.8 GetDscAction Sequence

The following sequence occurs between a client and a server during a GetDscAction request.

1. The client sends a GetDscAction request.
2. If the server requires the client to be authenticated, the server and client exchange access authentication HTTP headers as specified in [RFC2616] section 11.
3. If authentication is not required, or if authentication has succeeded, the server responds with a "200 OK" HTTP response.
4. The client closes the TCP connection to the server.

The following figure shows a message sequence with a single GetDscAction request.




Figure 8: Message sequence with a single GetDscAction request

5 Security

5.1 Security Considerations for Implementers

The protocol is vulnerable to a hijacking attack in which the attacker guesses the value of the *ConfigurationId* (as specified in section 3.1.5.1), *JobId*, and/or *ModuleName*, *ModuleVersion* (as specified in section 3.2.5.1), and the TCP port number used by the client. This approach works because the attacker can establish its own TCP connection to the server and send a request by using the victim's *ConfigurationId*, *JobId*, and/or *ModuleName*, *ModuleVersion* value. To mitigate the attack, make *ConfigurationId* and *JobId* random values. Also, if HTTP access authentication is used, the server ought to authenticate access at least once on each new URL or TCP connection.

5.2 Index of Security Parameters

Security parameter	Section
HTTP access authentication	As specified in section 2.1.

6 Appendix A: Full JSON Schema

```
{
  "title": "GetAction request schema",
  "type": "object",
  "properties": {
    "Checksum": {
      "type": ["string", "null"]
    },
    "ConfigurationName": {
      "type": ["string", "null"]
    },
    "NodeCompliant": {
      "type": "boolean"
    },
    "ChecksumAlgorithm": {
      "enum": ["SHA-256"],
      "description": "Checksum algorithm used to generate checksum"
    },
    "StatusCode": {
      "type": "integer"
    }
  },
  "required": ["Checksum", "NodeCompliant", "ChecksumAlgorithm"]
}

{
  "title": "GetAction response",
  "type": "object",
  "properties": {
    "value": {
      "enum": ["OK", "GetConfiguration", "Retry", "UpdateMetaConfiguration"],
      "required": "true"
    }
  }
}

{
  "title": "GetDscAction request schema (AgentID)",
  "type": "object",
  "properties": {
    "ClientStatus": {
      "type": "array",
      "minItems": 1,
      "items": [
        {
          "type": "object",
          "properties": {
            "Checksum": {
              "type": [ "string", "null" ]
            },
            "ConfigurationName": {
              "type": [ "string", "null" ]
            },
            "ChecksumAlgorithm": {
              "enum": [ "SHA-256" ],
              "description": "Checksum algorithm used to generate checksum"
            }
          }
        }
      ],
      "uniqueItems": true
    }
  }
}
}
```



```

{
  "title": "GetDscAction response",
  "type": "object",
  "properties": {
    "NodeStatus": {
      "enum": [ "OK", "RETRY", "GetConfiguration", "UpdateMetaConfiguration" ],
      "required": "true"
    },
    "Details": {
      "type": "array",
      "required": false,
      "items": [
        {
          "type": "object",
          "required": true,
          "properties": {
            "ConfigurationName": {
              "type": "string",
              "required": true
            },
            "Status": {
              "enum": [ "OK", "RETRY", "GetConfiguration",
"UpdateMetaConfiguration" ],
              "required": true
            }
          }
        }
      ]
    }
  }
}

{
  "title": "SendReport request schema",
  "type": "object",
  "properties": {
    "JobId": {
      "type": [ "string", "null" ],
      "required": "true"
    },
    "OperationType": {
      "type": [ "string", "null" ]
    },
    "RefreshMode": {
      "enum": [ "Push", "Pull" ]
    },
    "Status": {
      "type": [ "string", "null" ]
    },
    "LCMVersion": {
      "type": [ "string", "null" ]
    },
    "ReportFormatVersion": {
      "type": [ "string", "null" ]
    },
    "ConfigurationVersion": {
      "type": [ "string", "null" ]
    },
    "NodeName": {
      "type": [ "string", "null" ]
    },
    "IpAddress": {
      "type": [ "string", "null" ]
    },
    "StartTime": {
      "type": [ "string", "null" ]
    },
    "EndTime": {
      "type": [ "string", "null" ]
    }
  }
}

```

```

    "RebootRequested": {
      "enum": [ "True", "False" ]
    },
    "Errors": {
      "type": [ "string", "null" ]
    },
    "StatusData": {
      "type": [ "string", "null" ]
    },
    "AdditionalData": {
      "type": "array",
      "required": false,
      "items": [
        {
          "type": "object",
          "required": true,
          "properties": {
            "Key": {
              "type": "string",
              "required": true
            },
            "Value": {
              "type": "string",
              "required": true
            }
          }
        }
      ]
    }
  }
}

{
  "title": "RegisterDscAgent request",
  "type": "object",
  "properties": {
    "AgentInformation": {
      "type": "object",
      "properties": {
        "LCMVersion": {
          "type": [ "string", "null" ]
        },
        "NodeName": {
          "type": [ "string", "null" ]
        },
        "IPAddress": {
          "type": [ "string", "null" ]
        }
      }
    },
    "RegistrationInformation": {
      "type": "object",
      "properties": {
        "RegistrationMessageType" : {
          "type": [ "string", "null" ]
        },
        "CertificateInformation": {
          "type": "object",
          "properties": {
            "FriendlyName": {
              "type": [ "string", "null" ]
            },
            "Issuer": {
              "type": [ "string", "null" ]
            },
            "NotAfter": {
              "type": [ "string", "null" ]
            },
            "NotBefore": {
              "type": [ "string", "null" ]
            }
          }
        }
      }
    }
  }
}

```


7 Appendix B: Product Behavior

The information in this specification is applicable to the following Microsoft products or supplemental software. References to product versions include ~~released-service-packs~~updates to those products.

- Windows 7 operating system
- Windows Server 2008 R2 operating system
- Windows Server 2012 operating system
- Windows 8.1 operating system
- Windows Server 2012 R2 operating system
- Windows 10 operating system
- Windows Server 2016 operating system
- Windows Server operating system

Exceptions, if any, are noted ~~below in this section~~. If ~~a-an update version~~, service pack or ~~Quick-Fix Engineering (QFE)~~Knowledge Base (KB) number appears with ~~the~~ product ~~version, name, the~~ behavior changed in that ~~service-pack-or-QFE-update~~. The new behavior also applies to subsequent ~~service packs of the product~~updates unless otherwise specified. If a product edition appears with the product version, behavior is different in that product edition.

Unless otherwise specified, any statement of optional behavior in this specification that is prescribed using the terms "SHOULD" or "SHOULD NOT" implies product behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term "MAY" implies that the product does not follow the prescription.

<1> Section 2.2.2.4: The ConfigurationName header field is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, and Windows Server 2012 R2.

<2> Section 2.2.2.5: The ProtocolVersion header field is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and the Windows 10 v1507 operating system.

<3> Section 2.2.2.6: The AgentId header field is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and Windows 10 v1507.

<4> Section 2.2.2.7: The Authorization header field is available in is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and Windows 10 v1507.

<5> Section 2.2.2.8: The DSC-certificateRotation header field is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and Windows 10.

<6> Section 2.2.3.4: AgentId is not implemented in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, and Windows Server 2012 R2.

<7> Section 3.3.5.1.1.2: Retry is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, and Windows Server 2012 R2.

<8> Section 3.4: The SendStatusReport request is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, and Windows Server 2012 R2.

<9> Section 3.5: The GetStatusReport request is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, and Windows Server 2012 R2.

<10> Section 3.6: GetConfiguration Version 2.0 is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

<11> Section 3.7: GetModule Version 2.0 is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

<12> Section 3.8: GetDscAction is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

<13> Section 3.9: The RegisterDscAgent request is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

13<14> Section 3.9.5.1.1.1: The PublicKey value is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and Windows 10.

<15> Section 3.10: The SendReport request is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

<16> Section 3.11: GetReports is not available in Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2.

<17> Section 3.12: The CertificateRotation request is not available in Windows 7, Windows Server 2008 R2, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, and Windows 10.

8 Change Tracking

~~No table of This section identifies changes is available. The that were made to this document is either new or has had no changes since its the last release. Changes are classified as Major, Minor, or None.~~

The revision class **Major** means that the technical content in the document was significantly revised. Major changes affect protocol interoperability or implementation. Examples of major changes are:

- A document revision that incorporates changes to interoperability requirements.
- A document revision that captures changes to protocol functionality.

The revision class **Minor** means that the meaning of the technical content was clarified. Minor changes do not affect protocol interoperability or implementation. Examples of minor changes are updates to clarify ambiguity at the sentence, paragraph, or table level.

The revision class **None** means that no new technical changes were introduced. Minor editorial and formatting changes may have been made, but the relevant technical content is identical to the last released version.

The changes made to this document are listed in the following table. For more information, please contact dochelp@microsoft.com.

Section	Description	Revision class
2.2.2.8 DSC-certificateRotation	Added new section for this header.	Major
3.9.5.1.1.1 Request Body	Added description for the PublicKey value, and adjusted the field names in the description for CertificateInformation.	Major
3.12 CertificateRotation Details	Added new section and subsections for this request type.	Major
6 Appendix A: Full JSON Schema	Added definition for RotateCertificate request object.	Major
7 Appendix B: Product Behavior	Added Windows Server to the list of applicable products.	Major

9 Index

A

Applicability 9

C

[Capability negotiation](#) 9

[Certificaterotation](#)

[Abstract data model](#) 45

[Higher-layer triggered events](#) 45

[Initialization](#) 45

[Message processing events and sequencing rules](#) 45

[Other local events](#) 47

[Timer events](#) 47

[Timers](#) 45

Change tracking 62

Common data types 10

E

Examples

GetAction sequence 49

GetAction Sequence example 49

GetConfiguration sequence 48

GetConfiguration Sequence example 48

GetDscAction Sequence example 53

GetModule sequence 48

GetModule Sequence example 48

GetStatusReport Sequence example 51

RegisterDscAgent Sequence example 52

SendReport Sequence example 53

SendStatusReport sequence 50

SendStatusReport Sequence example 50

F

Fields - vendor-extensible 9

Full JSON schema 56

G

GetAction

abstract data model 20

higher-layer triggered events 20

initialization 20

message processing events and sequencing rules 20

other local events 22

timer events 22

timers 20

GetAction sequence example 49

Getaction versions 1.0 and 1.1

Abstract data model 20

Higher-layer triggered events 20

Initialization 20

Message processing events and sequencing rules 20

Other local events 22

Timer events 22

Timers 20

GetConfiguration

abstract data model 14

higher-layer triggered events 14

- initialization 14
- message processing events and sequencing rules 14
- other local events 17
- timer events 17
- timers 14
- GetConfiguration sequence example 48
- Getconfiguration version 2.0
 - Abstract data model 28
 - Higher-layer triggered events 28
 - Initialization 28
 - Message processing events and sequencing rules 28
 - Other local events 31
 - Timer events 31
 - Timers 28
- Getconfiguration versions 1.0 and 1.1
 - Abstract data model 14
 - Higher-layer triggered events 14
 - Initialization 14
 - Message processing events and sequencing rules 14
 - Other local events 17
 - Timer events 17
 - Timers 14
- Getdsaction version 2.0
 - Abstract data model 34
 - Higher-layer triggered events 34
 - Initialization 34
 - Message processing events and sequencing rules 34
 - Other local events 37
 - Timer events 37
 - Timers 34
- GetModule
 - abstract data model 17
 - highedr-layer triggered events 17
 - initialization 17
 - message processing events and sequencing rules 17
 - other local events 20
 - timer events 20
 - timers 17
- GetModule sequence example 48
- Getmodule version 2.0
 - Abstract data model 31
 - Higher-layer triggered events 31
 - Initialization 31
 - Message processing events and sequencing rules 31
 - Other local events 34
 - Timer events 34
 - Timers 31
- Getmodule versions 1.0 and 1.1
 - Abstract data model 17
 - Higher-layer triggered events 17
 - Initialization 17
 - Message processing events and sequencing rules 17
 - Other local events 20
 - Timer events 20
 - Timers 17
- Getreports version 2.0
 - Abstract data model 43
 - Higher-layer triggered events 43
 - Initialization 43
 - Message processing events and sequencing rules 43
 - Other local events 45
 - Timer events 45
 - Timers 43
- Getstatusreport versions 1.0 and 1.1
 - Abstract data model 25

- Higher-layer triggered events 26
- Initialization 25
- Message processing events and sequencing rules 26
- Other local events 27
- Timer events 27
- Timers 25

Glossary 7

H

HTTP headers 10

I

Implementer - security considerations 55

Index of security parameters 55

Informative references 8

Introduction 7

J

JSON schema 56

M

Messages

- data types 10
- transport 10

N

Namespaces 10

Normative references 8

O

Overview (synopsis) 8

P

Parameters - security index 55

Preconditions 8

Prerequisites 8

Product behavior 60

Protocol Details

- [CertificateRotation](#) 45
- GetAction 20
- GetAction Versions 1.0 and 1.1 20
- GetConfiguration 14
- GetConfiguration Version 2.0 28
- GetConfiguration Versions 1.0 and 1.1 14
- GetDscAction Version 2.0 34
- GetModule 17
- GetModule Version 2.0 31
- GetModule Versions 1.0 and 1.1 17
- GetReports Version 2.0 43
- GetStatusReport Versions 1.0 and 1.1 25
- RegisterDscAgent Version 2 37
- SendReport Version 2.0 40
- SendStatusReport 22
- SendStatusReport Versions 1.0 and 1.1 22

Protocol examples

- GetAction Sequence 49
- GetConfiguration Sequence 48

- GetDscAction Sequence 53
- GetModule Sequence 48
- GetStatusReport Sequence 51
- RegisterDscAgent Sequence 52
- SendReport Sequence 53
- SendStatusReport Sequence 50

R

- References
 - informative 8
 - normative 8
- Registerdscagent version 2
 - Abstract data model 37
 - Higher-layer triggered events 37
 - Initialization 37
 - Message processing events and sequencing rules 37
 - Other local events 39
 - Timer events 39
 - Timers 37
- Relationship to other protocols 8

S

- Schema - JSON 56
- Security
 - implementation 55
 - implementer considerations 55
 - parameter index 55
- Sendreport version 2.0
 - Abstract data model 40
 - Higher-layer triggered events 40
 - Initialization 40
 - Message processing events and sequencing rules 40
 - Other local events 42
 - Timer events 42
 - Timers 40
- SendStatusReport
 - abstract data model 22
 - higher-layer triggered events 23
 - initialization 23
 - message processing events and sequencing rules 23
 - timers 23
- SendStatusReport sequence example 50
- Sendstatusreport versions 1.0 and 1.1
 - Abstract data model 22
 - Higher-layer triggered events 23
 - Initialization 23
 - Message processing events and sequencing rules 23
 - Other local events 25
 - Timer events 25
 - Timers 23
- Standards assignments 9
- System overview - introduction 7

T

- Tracking changes 62
- Transport 10
 - common data types 10
 - namespaces 10

U

- URI parameters 12

V

Vendor-extensible fields 9

[Versioning_9](#)