[MS-SWN-Diff]:

Service Witness Protocol

Intellectual Property Rights Notice for Open Specifications Documentation

- **Technical Documentation.** Microsoft publishes Open Specifications documentation ("this documentation") for protocols, file formats, data portability, computer languages, and standards as well as overviews of the interaction among each of these technologies support. Additionally, overview documents cover inter-protocol relationships and interactions.
- **Copyrights**. This documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you maycan make copies of it in order to develop implementations of the technologies that are described in the Open Specifications this documentation and maycan distribute portions of it in your implementations usingthat use these technologies or in your documentation as necessary to properly document the implementation. You maycan also distribute in your implementation, with or without modification, any schema, IDL's schemas, IDLs, or code samples that are included in the documentation. This permission also applies to any documents that are referenced in the Open Specifications-documentation.
- No Trade Secrets. Microsoft does not claim any trade secret rights in this documentation.
- Patents. Microsoft has patents that maymight cover your implementations of the technologies described in the Open Specifications, documentation. Neither this notice nor Microsoft's delivery of thethis documentation grants any licenses under those patents or any other Microsoft patents. However, a given Open Specification maySpecifications document might be covered by the Microsoft Open Specifications Promise or the Microsoft Community Promise. If you would prefer a written license, or if the technologies described in the Open Specificationsthis documentation are not covered by the Open Specifications Promise or Community Promise, as applicable, patent licenses are available by contacting iplg@microsoft.com.
- **Trademarks**. The names of companies and products contained in this documentation maymight be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights. For a list of Microsoft trademarks, visit www.microsoft.com/trademarks.
- Fictitious Names. The example companies, organizations, products, domain names, e-mailemail addresses, logos, people, places, and events that are depicted in this documentation are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

Reservation of Rights. All other rights are reserved, and this notice does not grant any rights other than <u>as</u> specifically described above, whether by implication, estoppel, or otherwise.

Tools. The Open Specifications dodocumentation does not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments, you are free to take advantage of them. Certain Open Specifications documents are intended for use in conjunction with publicly available standardstandards specifications and network programming art, and assumes, as such, assume that the reader either is familiar with the aforementioned material or has immediate access to it.

Revision Summary

Date	Revision History	Revision Class	Comments
12/16/2011	1.0	New	Released new document.
3/30/2012	2.0	Major	Significantly changed the technical content.
7/12/2012	3.0	Major	Significantly changed the technical content.
10/25/2012	4.0	Major	Significantly changed the technical content.
1/31/2013	4.0	None	No changes to the meaning, language, or formatting of the technical content.
8/8/2013	5.0	Major	Significantly changed the technical content.
11/14/2013	6.0	Major	Significantly changed the technical content.
2/13/2014	7.0	Major	Significantly changed the technical content.
5/15/2014	7.0	None	No changes to the meaning, language, or formatting of the technical content.
6/30/2015	8.0	Major	Significantly changed the technical content.
10/16/2015	8.0	No Chang e <u>None</u>	No changes to the meaning, language, or formatting of the technical content.

Table of Contents

1	Intro	oduction	
	1.1	Glossary	
	1.2	References	
	1.2.1		
	1.2.2		
	1.3	Overview	
	1.4	Relationship to Other Protocols	7
	1.5	Prerequisites/Preconditions	
	1.6	Applicability Statement	
	1.7	Versioning and Capability Negotiation	
	1.8	Vendor Extensible Fields	
	1.9	Standards Assignments	
		-	
2		sages	
	2.1	Transport	
	2.2	Common Data Types	
	2.2.1	1 Data Types	9
	2.2	2.1.1 PCONTEXT_HANDLE	10
	2.2	2.1.2 PPCONTEXT_HANDLE	10
	2.2	2.1.3 PCONTEXT HANDLE SHARED	10
	2.2.2	2 Structures	10
	2.2	2.2.1 IPADDR_INFO	
		2.2.2 IPADDR_INFO_LIST	
	2.2	2.2.3 RESOURCE CHANGE	
		2.2.4 RESP_ASYNC_NOTIFY	
		2.2.5 WITNESS_INTERFACE_INFO	
		2.2.6 WITNESS_INTERFACE_LIST	
3		cocol Details	
3	3.1	Witness Server Details	15
3	3.1 3.1.1	Witness Server Details	15 15
3	3.1 3.1.1 3.1	Witness Server Details	15 15 15
3	3.1 3.1.1 3.1 3.1	Witness Server Details	15 15 15 15
3	3.1 3.1.1 3.1 3.1	Witness Server Details	15 15 15 15 15
3	3.1 3.1.1 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model	15 15 15 15 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model	15 15 15 15 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model	15 15 15 15 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model	15 15 15 15 16 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model	15 15 15 15 16 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1 3.1.2 3.1	Witness Server Details 1 Abstract Data Model 1.1.1 Global	15 15 15 15 16 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1 3.1.2 3.1	Witness Server Details	15 15 15 15 16 16 16 16
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1 3.1,2 3.1 3.1 3.1	Witness Server Details 1 Abstract Data Model 1.1.1 Global	15 15 15 15 16 16 16 16 17
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 16 17 17
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 16 17 17
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 16 17 17 17
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 17 17 17 17
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details Abstract Data Model 1.1.1 Global 1.1.2 Per Interface in InterfaceList 1.1.3 Per WitnessRegistration in WitnessRegistrationList 1.1.4 Per Notification in PendingChangeNotifications 1.1.5 PendingMoveNotification 1.1.6 PendingShareMoveNotification 1.1.7 PendingIPNotification 2 Timers 1.2.1 Unused Registration Timer 1.2.2 AsyncNotify Pending Timer 1.2.2 AsyncNotify Pending Timer 3 Initialization 4 Message Processing Events and Sequencing Rules 1.4.1 WitnessrGetInterfaceList (Opnum 0) 1.4.2 WitnessrRegister (Opnum 1) 1.4.3 WitnessrUnRegister (Opnum 2) 1.4.4 WitnessrAsyncNotify (Opnum 3)	15 15 15 15 16 16 16 16 17 17 17 17 19 19
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details Abstract Data Model. 1.1.1 Global	15 15 15 15 16 16 16 16 17 17 17 17 19 21
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details Abstract Data Model 1.1.1 Global 1.1.2 Per Interface in InterfaceList 1.1.3 Per WitnessRegistration in WitnessRegistrationList 1.1.4 Per Notification in PendingChangeNotifications 1.1.5 PendingMoveNotification 1.1.6 PendingShareMoveNotification 1.1.7 PendingIPNotification 2 Timers 1.2.1 Unused Registration Timer 1.2.2 AsyncNotify Pending Timer 1.2.2 AsyncNotify Pending Timer 3 Initialization 4 Message Processing Events and Sequencing Rules 1.4.1 WitnessrGetInterfaceList (Opnum 0) 1.4.2 WitnessrRegister (Opnum 1) 1.4.3 WitnessrUnRegister (Opnum 2) 1.4.4 WitnessrAsyncNotify (Opnum 3) 1.4.5 WitnessrRegisterEx (Opnum 4) Timer Events	15 15 15 15 16 16 16 16 17 17 17 17 19 21 24
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details Abstract Data Model 1.1.1 Global 1.1.2 Per Interface in InterfaceList 1.1.3 Per WitnessRegistration in WitnessRegistrationList 1.1.4 Per Notification in PendingChangeNotifications 1.1.5 PendingMoveNotification 1.1.6 PendingShareMoveNotification 1.1.7 PendingIPNotification 2 Timers 1.2.1 Unused Registration Timer 1.2.2 AsyncNotify Pending Timer 3 Initialization 4 Message Processing Events and Sequencing Rules 1.4.1 WitnessrGetInterfaceList (Opnum 0) 1.4.2 WitnessrRegister (Opnum 1) 1.4.3 WitnessrUnRegister (Opnum 2) 1.4.4 WitnessrAsyncNotify (Opnum 3) 1.4.5 WitnessrRegisterEx (Opnum 4) 5 Timer Events 1.5.1 Unused Registration Timer Event	15 15 15 15 16 16 16 16 17 17 17 19 21 24 27
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details Abstract Data Model 1.1.1 Global 1.1.2 Per Interface in InterfaceList 1.1.3 Per WitnessRegistration in WitnessRegistrationList 1.1.4 Per Notification in PendingChangeNotifications 1.1.5 PendingMoveNotification 1.1.6 PendingShareMoveNotification 1.1.7 PendingIPNotification 2 Timers 1.2.1 Unused Registration Timer 1.2.2 AsyncNotify Pending Timer 3 Initialization 4 Message Processing Events and Sequencing Rules 1.4.1 WitnessrGetInterfaceList (Opnum 0) 1.4.2 WitnessrRegister (Opnum 1) 1.4.3 WitnessrUnRegister (Opnum 2) 1.4.4 WitnessrAsyncNotify (Opnum 3) 1.4.5 WitnessrRegisterEx (Opnum 4) Timer Events 1.5.1 Unused Registration Timer Event 1.5.2 AsyncNotify Pending Timer Event	15 15 15 15 16 16 16 16 17 17 17 17 21 21 24 27
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 16 17 17 17 17 21 24 27 27
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 15 16 16 16 16 17 17 17 21 21 24 27 27
3	3.1 3.1.1 3.1 3.1 3.1 3.1 3.1,3 3.1,3 3.1,4 3.1 3.1,3 3.1,4 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1,5 3.1 3.1 3.1 3.1 3.1 3.1 3.1 3.1	Witness Server Details	15 15 15 16 16 16 16 16 17 17 17 21 21 27 27 27

	3.1.6.4	Server Application Notifies of an IP Address Being Added, Removed, Enable	d or
		Disabled	
	3.1.6.5	Transport Connection Shutdown	29
	3.2 Wit	ness Client Details	
	3.2.1	Abstract Data Model	29
	3.2.1.1	Global	29
	3.2.1.2	Per WitnessRegistration	. 29
	3.2.2	Timers	
	3.2.3	Initialization	
	3.2.4	Message Processing Events and Sequencing Rules	
	3.2.4.1		
	3.2.4.2		
	3.2.4.3	Application Requests Witness UnRegister	33
	3.2.5	Timer Events	
	3.2.6	Other Local Events	34
4	Protocol	Examples	35
		gistering Notification Changes from the Witness Server	
	_		
		curity Considerations for Implementers	
	5.2 Ind	ex of Security Parameters	38
6	Appendi	x A: Full IDL	39
	• •		
7	Appendi	x B: Product Behavior	41
8	Change '	Tracking	. 43
9	Index		45

1 Introduction

The Service Witness Protocol is a remote procedure call (RPC)-based protocol that is used to promptly notify a client of resource changes that have occurred on a highly available server.

Sections 1.5, 1.8, 1.9, 2, and 3 of this specification are normative and can contain the terms MAY, SHOULD, MUST, MUST NOT, and SHOULD NOT as defined in [RFC2119]. Sections 1.5 and 1.9 are also normative but do not contain those terms. All other sections and examples in this specification are informative.

1.1 Glossary

The This document uses the following terms are specific to this document:

- **fully qualified domain name (FQDN)**: An unambiguous domain name (2) that gives an absolute location in the Domain Name System's (DNS) hierarchy tree, as defined in [RFC1035] section 3.1 and [RFC2181] section 11.
- **Internet Protocol version 4 (IPv4)**: An Internet protocol that has 32-bit source and destination addresses. IPv4 is the predecessor of IPv6.
- **Internet Protocol version 6 (IPv6)**: A revised version of the Internet Protocol (IP) designed to address growth on the Internet. Improvements include a 128-bit IP address size, expanded routing capabilities, and support for authentication (2) and privacy.
- **Microsoft Interface Definition Language (MIDL)**: The Microsoft implementation and extension of the OSF-DCE Interface Definition Language (IDL). **MIDL** can also mean the Interface Definition Language (IDL) compiler provided by Microsoft. For more information, see [MS-RPCE].
- **NetBIOS name**: A 16-byte address that is used to identify a NetBIOS resource on the network. For more information, see [RFC1001] and [RFC1002].
- **remote procedure call (RPC)**: A context-dependent term commonly overloaded with three meanings. Note that much of the industry literature concerning RPC technologies uses this term interchangeably for any of the three meanings. Following are the three definitions: (*) The runtime environment providing remote procedure call facilities. The preferred usage for this meaning is "RPC runtime". (*) The pattern of request and response message exchange between two parties (typically, a client and a server). The preferred usage for this meaning is "RPC exchange". (*) A single message from an exchange as defined in the previous definition. The preferred usage for this term is "RPC message". For more information about RPC, see [C706].
- **RPC context handle**: A representation of state maintained between a remote procedure call (RPC) client and server. The state is maintained on the server on behalf of the client. An RPC context handle is created by the server and given to the client. The client passes the RPC context handle back to the server in method calls to assist in identifying the state. For more information, see [C706].
- **RPC server**: A computer on the network that waits for messages, processes them when they arrive, and sends responses using RPC as its transport acts as the responder during a remote procedure call (RPC) exchange.
- **RPC transport**: The underlying network services used by the remote procedure call (RPC) runtime for communications between network nodes. For more information, see [C706] section 2.
- **Transmission Control Protocol (TCP)**: A protocol used with the Internet Protocol (IP) to send data in the form of message units between computers over the Internet. TCP handles keeping track of the individual units of data (called packets) that a message is divided into for efficient routing through the Internet.

universally unique identifier (UUID): A 128-bit value. UUIDs can be used for multiple purposes, from tagging objects with an extremely short lifetime, to reliably identifying very persistent objects in cross-process communication such as client and server interfaces, manager entry-point vectors, and RPC objects. UUIDs are highly likely to be unique. UUIDs are also known as globally unique identifiers (GUIDs) and these terms are used interchangeably in the Microsoft protocol technical documents (TDs). Interchanging the usage of these terms does not imply or require a specific algorithm or mechanism to generate the UUID. Specifically, the use of this term does not imply or require that the algorithms described in [RFC4122] or [C706] must be used for generating the UUID.

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as defined in [RFC2119]. All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

Links to a document in the Microsoft Open Specifications library point to the correct section in the most recently published version of the referenced document. However, because individual documents in the library are not updated at the same time, the section numbers in the documents may not match. You can confirm the correct section numbering by checking the Errata.

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information.

[C706] The Open Group, "DCE 1.1: Remote Procedure Call", C706, August 1997, https://www2.opengroup.org/ogsys/catalog/c706

[MS-DTYP] Microsoft Corporation, "Windows Data Types".

[MS-ERREF] Microsoft Corporation, "Windows Error Codes".

[MS-RPCE] Microsoft Corporation, "Remote Procedure Call Protocol Extensions".

[MS-SRVS] Microsoft Corporation, "Server Service Remote Protocol".

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, http://www.rfc-editor.org/rfc/rfc2119.txt

1.2.2 Informative References

[MS-SMB2] Microsoft Corporation, "Server Message Block (SMB) Protocol Versions 2 and 3".

1.3 Overview

In highly available systems, there can be many instances of a service (for instance an SMB3 file service [MS-SMB2]) running on a server or group of servers. These service instances are accessed by clients through network DNS names and associated IP addresses.

The Service Witness Protocol enables a client application (for instance, an SMB3 client) to receive prompt and explicit notifications about the failure or recovery of a network name and associated services, rather than relying on slower detection mechanisms such as time-outs and keep-alives.

The Service Witness Protocol is an independent protocol which is used alongside other protocols, as illustrated by the following figure.




Figure 1: Witness clients communicating with Witness servers

1.4 Relationship to Other Protocols

This protocol depends on the RPC transport and uses RPC over TCP, as specified in section 2.1.

1.5 Prerequisites/Preconditions

The Service Witness Protocol is an RPC interface and, as a result, has the prerequisites that are described in [MS-RPCE] section 1.5 as being common to RPC interfaces.

1.6 Applicability Statement

This protocol applies in the following environments, where it is important that:

- The client promptly detects when a resource has failed, and is now available for reconnection.
- The administrator controls the client use of server resources, for instance, to achieve load-balancing or during server maintenance periods.

1.7 Versioning and Capability Negotiation

The protocol supports versioning negotiation. The current protocol supports two versions.

Version	Value
Witness protocol version 1	0x00010001
Witness protocol version 2	0x00020000

1.8 Vendor Extensible Fields

This protocol does not define any vendor-extensible fields.

This protocol uses Win32 error codes as defined in [MS-ERREF] section 2.2. Vendors SHOULD reuse those values with their indicated meaning. Choosing any other value runs the risk of a collision in the future.

1.9 Standards Assignments

Parameter	Value	Reference
UUID for Witness	ccd8c074-d0e5-4a40-92b4-d074faa6ba28	[C706]

2 Messages

2.1 Transport

This protocol MUST use the **UUID** as specified in section 1.9. The RPC version number is 1.0.

This protocol allows any user to establish a connection to the **RPC server**. The protocol uses the underlying RPC protocol to retrieve the identity of the caller that made the method call, as specified in [MS-RPCE] section 3.3.3.4.3. The server SHOULD use this identity to perform method-specific access checks as specified in section 3.1.4.

2.2 Common Data Types

In addition to RPC base types defined in [C706] and [MS-RPCE], the data types that follow are defined in the **Microsoft Interface Definition Language (MIDL)** specification for this RPC interface.

The following data types are specified in [MS-DTYP]:

DataType name	Section
BOOLEAN	section 2.2.4
DWORD	section 2.2.9
LPWSTR	section 2.2.36
PBYTE	section 2.2.6
UINT	section 2.2.46
UINT32	section 2.2.49
ULONG	section 2.2.51
USHORT	section 2.2.58
WCHAR	section 2.2.60

2.2.1 Data Types

DataType name	Section	Description
PCONTEXT_HANDLE	2.2.1.1	An RPC context handle returned by the WitnessrRegister method, to be provided as an input parameter to the WitnessrUnRegister method.
PCONTEXT_HANDLE_SHARED	2.2.1.3	An RPC context handle returned by the WitnessrRegister method, to be provided as an input parameter to the WitnessrAsyncNotify method.
PPCONTEXT_HANDLE	2.2.1.2	A reference to PCONTEXT_HANDLE.

2.2.1.1 PCONTEXT_HANDLE

PCONTEXT_HANDLE: An RPC context handle, as specified in [C706] Chapter 6, returned by the WitnessrRegister method, to be provided as an input parameter to the WitnessrUnRegister method.

typedef [context handle] void* PCONTEXT HANDLE;

2.2.1.2 PPCONTEXT_HANDLE

PPCONTEXT_HANDLE: A reference to PCONTEXT_HANDLE, as specified in section 2.2.1.1.

typedef [ref] PCONTEXT_HANDLE *PPCONTEXT_HANDLE;

2.2.1.3 PCONTEXT_HANDLE_SHARED

PCONTEXT_HANDLE_SHARED: An RPC context handle, as specified in [C706] Chapter 6, returned by the WitnessrRegister method, to be provided as a parameter to the WitnessrAsyncNotify method.

typedef [context handle] PCONTEXT HANDLE PCONTEXT HANDLE SHARED;


2.2.2 Structures

Unless otherwise specified, multiple-byte fields (16-bit, 32-bit, and 64-bit fields) MUST be transmitted in little-endian order (least-significant byte first) for the structures specified in section 2.2.2.1 (IPADDR_INFO), 2.2.2.2 (IPADDR_INFO_LIST), and 2.2.2.3 (RESOURCE_CHANGE). Other structures defined in this section use RPC encoding.

Structure name	Section	Description
IPADDR_INFO	2.2.2.1	The IPADDR_INFO structure specifies the IP addresses of the interface.
IPADDR_INFO_LIST	2.2.2.2	The IPADDR_INFO_LIST structure contains the list of available IP addresses on the destination Interface group.
RESOURCE_CHANGE	2.2.2.3	The server notifies the registered client of resource state changes through the RESOURCE_CHANGE structure.
RESP_ASYNC_NOTIFY	2.2.2.4	The RESP_ASYNC_NOTIFY structure contains the resource change type.
WITNESS_INTERFACE_INFO	2.2.2.5	The WITNESS_INTERFACE_INFO structure specifies the IP addresses of the interface.
WITNESS_INTERFACE_LIST	2.2.2.6	The WITNESS_INTERFACE_LIST structure specifies the list of interfaces available for witness registration.

2.2.2.1 IPADDR_INFO

The IPADDR INFO structure specifies the IP addresses of the interface.



Flags (4 bytes): The Flags field SHOULD<1> be set to a combination of one or more of the following values.


Value	Description
0x00000001 IPADDR_V4	If set, the IPV4 field contains a valid address. When this bit is set, the IPADDR_IPV6 bit MUST NOT be set.
0x00000002 IPADDR_V6	If set, the IPV6 field contains a valid address. When this bit is set, the IPADDR_IPV4 bit MUST NOT be set.
0x00000008 IPADDR_ONLINE	If set, the IPV4 or IPV6 address is available. This flag is applicable only for the servers implementing version 2.
0x0000010 IPADDR_OFFLINE	If set, the IPV4 or IPV6 address is not available. This flag is applicable only for the server implementing version 2.

IPV4 (4 bytes): The IPv4 address of the interface, if the IPADDR_V4 flag is set in the Flags field.

IPV6 (16 bytes): The IPv6 address of the interface, if the IPADDR_V6 flag is set in the Flags field.

2.2.2.2 IPADDR_INFO_LIST

The IPADDR_INFO_LIST structure contains a list of available IP addresses on the destination Interface group.



Length (4 bytes): The size of the IPADDR_INFO_LIST structure, in bytes.


Reserved (4 bytes): This field MUST NOT be used and MUST be reserved. The server MUST set this field to 0, and the client MUST ignore it on receipt.

IPAddrInstances (4 bytes): The number of IPADDR_INFO structures in the **IPAddrInfo** member.

IPAddrInfo (variable): An array of one or more IPADDR_INFO structures, as specified in section 2.2.2.1, indicating the IP addresses of the destination Interface group.

2.2.2.3 RESOURCE_CHANGE

The server notifies the registered client of resource state changes through the use of the RESOURCE CHANGE structure.



Length (4 bytes): The size of the resource change notification, in bytes.

ChangeType (4 bytes): Specifies state change of the resource. The following values are used to specify the change type.

Value	Meaning
0x00000000	RESOURCE_STATE_UNKNOWN
0x00000001	RESOURCE_STATE_AVAILABLE
0x000000FF	RESOURCE_STATE_UNAVAILABLE

ResourceName (variable): The null terminated resource name on which the change has been detected. This MUST be either the NetName or IP address provided in a WitnessrRegister call, or an InterfaceGroupName returned to the client in a WitnessrGetInterfaceList response.

2.2.2.4 RESP_ASYNC_NOTIFY

The RESP_ASYNC_NOTIFY structure contains the resource change type.

```
typedef struct _RESP_ASYNC_NOTIFY {
    UINT MessageType;
    UINT Length;
    UINT NumberOfMessages;
    [size_is(Length)] [unique] PBYTE MessageBuffer;
} RESP ASYNC NOTIFY, *PRESP ASYNC NOTIFY;
```

MessageType: Specifies the notification type. This field MUST contain one of the following values.

Value	Meaning
1	RESOURCE_CHANGE_NOTIFICATION
2	CLIENT_MOVE_NOTIFICATION
3	SHARE_MOVE_NOTIFICATION This value is applicable only for the server implementing version 2.
4	IP_CHANGE_NOTIFICATION This value is applicable only for the server implementing version 2.

Length: Specifies the size of the MessageBuffer field, in bytes.

NumberOfMessages: Total number of notifications in the **MessageBuffer** field.

MessageBuffer: Contains an array of notification information structures whose type is determined by the **MessageType** field.

2.2.2.5 WITNESS_INTERFACE_INFO

The WITNESS_INTERFACE_INFO structure specifies the IP addresses of the interface.

```
typedef struct _WITNESS_INTERFACE_INFO {
   WCHAR InterfaceGroupName[260];
   ULONG Version;
   USHORT State;
   ULONG IPV4;
   USHORT IPV6[8];
   UINT Flags;
} WITNESS INTERFACE INFO, *PWITNESS INTERFACE INFO;
```

InterfaceGroupName: The null-terminated string that specifies a name of the interface group.

Version: The current version of the Witness Service running on the server.

State: The current state of the interface. This field MUST contain one of the following values:

Value	Meaning
UNKNOWN 0x0000	The state of the interface is unknown.
AVAILABLE 0x0001	The interface is available.
UNAVAILABLE 0x00FF	The interface is unavailable.

IPV4: The IPv4 address of the interface, if the IPv4 flag is set in **Flags** field.

IPV6: The IPv6 address of the interface, if the IPv6 flag is set in Flags field.

Flags: The **Flags** field specifies information about the interface. This field MUST be set to combination of zero or more of the following values:

Value	Meaning
IPv4 0x00000001	If set, the IPV4 field contains a valid address.
IPv6 0x00000002	If set, the IPV6 field contains a valid address.
INTERFACE_WITNESS 0x00000004	If set, the interface is available for witness registration. If not set, the interface MUST NOT be used for witness registration.

2.2.2.6 WITNESS_INTERFACE_LIST

The WITNESS_INTERFACE_LIST structure specifies the list of interfaces available for witness registration.

```
typedef struct _WITNESS_INTERFACE_LIST {
    UINT NumberOfInterfaces;
    [size_is(NumberOfInterfaces)] [unique] PWITNESS_INTERFACE_INFO InterfaceInfo;
} WITNESS INTERFACE LIST, *PWITNESS INTERFACE LIST;
```

NumberOfInterfaces: The number of WITNESS_INTERFACE_INFO structures in InterfaceInfo.

InterfaceInfo: Contains an array of WITNESS_INTERFACE_INFO structures, as specified in section 2.2.2.5.

3 Protocol Details

3.1 Witness Server Details

The server responds to messages it receives from the client and also produces notifications as requested by the client. The server performs additional actions in response to administrative, configuration, and status changes on the machine, as driven by applications local to the server.

3.1.1 Abstract Data Model

This section describes a conceptual model of possible data organization that an implementation maintains to participate in this protocol. The organization is provided to facilitate the explanation of how the protocol behaves. This specification does not mandate that implementations adhere to this model as long as their external behaviors are consistent with that described in this specification.

3.1.1.1 Global

The server implements the following properties:

- InterfaceList: A list of available Interfaces as specified in section 3.1.1.2.
- WitnessRegistrationList: A list of witness registrations on the server, as specified in section 3.1.1.3.
- **WitnessServiceVersion**: The highest Witness protocol version supported by the Witness Service. The value MUST be one of those listed in section 1.7.
- ServerGlobalName: A hostname by which clients access the server being witnessed.

3.1.1.2 Per Interface in InterfaceList

- **InterfaceGroupName**: The name of the interface group, in the form of a **NetBIOS name**.
- **State**: The state of the interface. This MUST be set to one of the values specified in section 2.2.2.5.
- IPv4Address: An IPv4 address of the interface, if any.
- **IPv6Address**: An IPv6 address of the interface, if any.

3.1.1.3 Per WitnessRegistration in WitnessRegistrationList

The server implements the following properties per witness registration.

- WitnessClientName: A null-terminated string containing the name of the client.
- NetworkName: The NetName specified in the client registration call.
- **IPAddress**: An IP address specified in the client registration call.
- RegistrationKey: A unique value assigned by the server for this registration, in the form of context_handle, as specified in section 2.2.1.1.
- PendingChangeNotifications: A list of change notifications pending for this registration.
- **PendingMoveNotification:** The most recent move notification, if any, pending for this registration.

If the server implements version 2 of the protocol, the server also implements the following properties:

- WitnessClientVersion: The Witness protocol version implemented by the client.
- ShareName: The ShareName specified in the client registration call.
- **ShareNameNotificationRequired**: A Boolean when set; indicates that this registration requires notifications based on the *ShareName*.
- **IPNotificationRequired**: A Boolean when set; indicates that this registration requires notifications based on the IP addresses changes on the server associated with *NetName*.
- PendingShareMoveNotification: The most recent share move notification, if any, pending for this registration.
- **PendingIPNotification**: The most recent IP change notification, if any, pending for this registration.
- **KeepAliveTime**: The maximum amount of the time, in seconds, the server can hold the pending asynchronous notification.
- **LastUseTime**: The time at which the server received a registration request, an asynchronous notify request, or at which time the server sent a response to an asynchronous notification.
- **IsAsyncNotifyRegistered**: A Boolean flag indicating whether asynchronous notification is registered or not.

3.1.1.4 Per Notification in PendingChangeNotifications

- **ResourceName**: The name of the resource whose state has changed.
- **NewState**: The new resource state.

3.1.1.5 PendingMoveNotification

• **Destination**: A null-terminated string describing the resource to move to.

3.1.1.6 PendingShareMoveNotification

If the server implements version 2 of the protocol, the server also implements the following:

Destination: A null-terminated string describing the resource the share has been moved to.

3.1.1.7 PendingIPNotification

If the server implements version 2 of the protocol, the server also implements the following:

ChangeIndication: A null-terminated string describing the IP changes on the server.

3.1.2 Timers

3.1.2.1 Unused Registration Timer

If the server implements version 2 of the protocol, it MUST implement this timer.

This timer controls the amount of time that a registration can stay unused, in other words, the time for which the registration is permitted to remain without registering for any asynchronous

notifications. The server MUST schedule this timer periodically with an implementation-specific interval and remove unused registrations.

3.1.2.2 AsyncNotify Pending Timer

If the server implements version 2 of the protocol, it MUST implement this timer.

This timer controls the scheduling of periodic searches for pending asynchronous notifications that have passed their expiration time. This value is based on the **KeepAliveTimeout** value provided by the client as specified in section 3.1.4.5.

3.1.3 Initialization

The server MUST initialize **WitnessRegistrationList** to empty.

The server MUST initialize **InterfaceList** in an implementation-specific manner from the configuration store.

The server MUST initialize **WitnessServiceVersion** to the highest Witness protocol version supported by the server.<2>

The server MUST initialize **ServerGlobalName** with an administrator-defined string.

3.1.4 Message Processing Events and Sequencing Rules

The Witness interface defines the following methods:

Method	Description
WitnessrGetInterfaceList	The WitnessrGetInterfaceList method returns information about the interfaces to which witness client connections can be made. Opnum: 0
WitnessrRegister	The WitnessrRegister method allows the witness client to register for notifications from the server. Opnum: 1
WitnessrUnRegister	The WitnessrUnRegister method allows the client to unregister for notifications from the server. Opnum: 2
WitnessrAsyncNotify	The WitnessrAsyncNotify method is used by the client to request notification of resource changes from the server. Opnum: 3
WitnessrRegisterEx	The WitnessrRegisterEx method allows the witness client to register for notifications from the server for a specific share and with optional flags. This opnum is only applicable for Witness protocol version 2. Opnum: 4

For all methods, the server SHOULD<3> enforce security measures to verify that the caller has the required permissions to execute any method. If the server enforces security measures, and the caller does not have the required credentials, then the server MUST fail the call and return ERROR_ACCESS_DENIED. For more details about determining the identity of the caller for the purpose of performing an access check, see [MS-RPCE] section 3.3.3.1.3.

3.1.4.1 WitnessrGetInterfaceList (Opnum 0)

The WitnessrGetInterfaceList method returns information about the interfaces to which witness client connections can be made.

```
DWORD WitnessrGetInterfaceList(
        [in] handle_t Handle,
        [out] PWITNESS INTERFACE LIST* InterfaceList);
```

Handle: An RPC binding handle [C706].

InterfaceList: A pointer to a PWITNESS_INTERFACE_LIST, as specified in section 2.2.2.6.

Return Values: Returns 0x00000000 (ERROR_SUCCESS) on success or a nonzero error code, as specified in [MS-ERREF] section 2.2. The most common error codes are listed in the following table.

Return value/code	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x00000057 ERROR_INVALID_PARAMETER	The parameter is incorrect.
0x00000103 ERROR_NO_MORE_ITEMS	No more data is available.
0x0000000E ERROR_OUTOFMEMORY	There is not enough storage space to complete the operation.

If there are no entries in the **InterfaceList**, the server MUST fail the request and return the error code ERROR_NO_MORE_ITEMS.

If no entry in the InterfaceList has a State of AVAILABLE, the server MUST wait until at least one entry enters that State, as specified in section 3.1.6.1.

For each **Interface** in the **InterfaceList**, the server MUST construct a WITNESS_INTERFACE_INFO structure as follows:

- The **InterfaceGroupName** field of the WITNESS_INTERFACE_INFO structure MUST be set to **Interface.InterfaceGroupName**.
- The State field MUST be set to Interface.State.
- The Version field MUST be set to WitnessServiceVersion.
- If **Interface.IPv4Address** is not empty, the **IPV4** field MUST be set to **Interface.IPv4Address**, and IPv4 flag MUST be set in the **Flags** field.
- If Interface.IPv6Address is not empty, the IPV6 field MUST be set to Interface.IPv6Address, and IPv6 flag MUST be set in the Flags field.
- In an implementation-dependent manner, the server MUST determine if the IPv4Address or IPv6Address match any interface which is hosted on the server and the server is also running

this Witness Service instance. If the address is not hosted on the local server, the INTERFACE_WITNESS flag MUST be set in the **Flags** field. Otherwise, the flag MUST NOT be set.

The server MUST construct the WITNESS_INTERFACE_LIST structure as follows:

- All WITNESS_INTERFACE_INFO structures MUST be copied into the InterfaceInfo field of the WITNESS_INTERFACE_LIST structure.
- The NumberOfInterfaces field of the WITNESS_INTERFACE_LIST structure MUST be set to the number of interfaces provided by InterfaceInfo.

The WITNESS_INTERFACE_LIST structures MUST be copied into the *InterfaceList* parameter.

The server MUST return ERROR SUCCESS and the *InterfaceList* parameter to the caller.

3.1.4.2 WitnessrRegister (Opnum 1)

The WitnessrRegister method allows the witness client to register for resource state change notifications of a NetName and IPAddress. The client can subsequently call the WitnessrAsyncNotify method to receive notifications when there is a state change on any of these resources.

```
DWORD WitnessrRegister(
        [in] handle_t Handle,
        [out] PPCONTEXT_HANDLE ppContext,
        [in] ULONG Version,
        [in] [string] [unique] LPWSTR NetName,
        [in] [string] [unique] LPWSTR IpAddress,
        [in] [string] [unique] LPWSTR ClientComputerName);
```

Handle: An RPC binding handle [C706].

ppContext: A context handle of type PPCONTEXT_HANDLE, as specified in section 2.2.1.2, that identifies the client on the server.

Version: The version of the Witness protocol currently in use by the client.

NetName: A pointer to a null-terminated string that specifies the name of the resource for which the client requires notifications.

IpAddress: A pointer to a null-terminated string that specifies the IP address to which the client application connection is established.

ClientComputerName: A pointer to a null-terminated string that is used to identify the Witness client.

Return Values: Returns 0x00000000 (ERROR_SUCCESS) on success or a nonzero error code, as specified in [MS-ERREF] section 2.2. The most common error codes are listed in the following table.

Return value/code	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x000005AA	Insufficient system resources exist to complete the requested service.

Return value/code	Description
ERROR_NO_SYSTEM_RESOURCES	
0x00000057 ERROR_INVALID_PARAMETER	The parameter is incorrect.
0x0000139F ERROR_INVALID_STATE	The specified resource state is invalid.
0x0000051A ERROR_REVISION_MISMATCH	The client request contains an invalid Witness protocol version.

If the **Version** field of the request is not 0x00010001, the server MUST stop processing the request and return the error code ERROR_REVISION_MISMATCH.

<u>If NetName</u>, <u>IpAddress</u> or <u>ClientComputerName</u> is <u>NULL</u>, the server <u>MUST</u> fail the request and return the error code ERROR INVALID PARAMETER.

If the *NetName* parameter is not equal to **ServerGlobalName**, the server MUST fail the request and return the error code ERROR_INVALID_PARAMETER.

The server MUST enumerate the shares by calling **NetrShareEnum** as specified in [MS-SRVS] section 3.1.4.8. In the enumerated list, if any of the shares has shi* type set to STYPE CLUSTER SOFS, as specified in [MS-SRVS] section 2.2.2.4, the server MUST search for an **Interface** in **InterfaceList**, where **Interface.IPv4Address** or **Interface.IPv6Address** matches the *IpAddress* parameter based on its format. If no matching entry is found, the server MUST fail the request and return the error code ERROR_INVALID_STATE.

The server MUST enumerate the shares by calling **NetrShareEnum** as specified in [MS_SRVS] section 3.1.4.8. In the enumerated list, if any of the shares have shi*_type set to STYPE_CLUSTER_SOFS, as specified in [MS_SRVS] section 2.2.2.4, the server MUST fail the request and return the error code ERROR_INVALID_STATE.

The server MUST create a **WitnessRegistration** entry as follows and insert it into the **WitnessRegistrationList**.

- WitnessRegistration.WitnessClientName MUST be set to the ClientComputerName parameter.
- WitnessRegistration.NetworkName MUST be set to the NetName parameter.
- **WitnessRegistration.IPAddress** MUST be set to the *IPAddress* parameter.
- WitnessRegistration.RegistrationKey MUST be set to a UUID generated by the server.
- WitnessRegistration.PendingChangeNotifications and
 WitnessRegistration.PendingMoveNotification MUST be set to empty.

If **WitnessServiceVersion** is 0x00020000, the server MUST set the following values in **WitnessRegistration** entry:

- WitnessRegistration.WitnessClientVersion MUST be set to the value of the Version parameter value in the request.
- WitnessRegistration.ShareName MUST be set to empty.
- WitnessRegistration.ShareNameNotificationRequired MUST be set to FALSE.
- WitnessRegistration.IPNotificationRequired MUST be set to FALSE.
- WitnessRegistration.PendingShareMoveNotification MUST be set to empty

WitnessRegistration.PendingIPNotification MUST be set to empty.

The server MUST copy the **WitnessRegistration.RegistrationKey** into the *ppContext* parameter.

The server MUST return ERROR_SUCCESS and the ppContext parameter to the caller.

3.1.4.3 WitnessrUnRegister (Opnum 2)

The WitnessrUnRegister method allows the client to unregister for notifications from the server. The Witness Service removes its internal state of the registration and no longer notifies the client in the event of any resource state changes.

```
DWORD WitnessrUnRegister(
       [in] handle_t Handle,
       [in] PCONTEXT HANDLE pContext);
```

Handle: An RPC binding handle [C706].

pContext: A context handle of type PCONTEXT_HANDLE, specified in section 2.2.1.1, that identifies the client on the server.

Return Values: Returns 0x00000000 (ERROR_SUCCESS) on success or a nonzero error code, as specified in [MS-ERREF] section 2.2. The most common error codes are listed in the following table.

Return value/code	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x00000490 ERROR_NOT_FOUND	The specified CONTEXT_HANDLE is not found.

The server MUST search for the **WitnessRegistration** in **WitnessRegistrationList**, where **WitnessRegistration.RegistrationKey** matches the *pContext* parameter.

If no matching entry is found, the server SHOULD<4> stop processing the request and return the error code ERROR_NOT_FOUND.

If the matching entry is found, the server MUST remove the **WitnessRegistration** entry from the **WitnessRegistrationList** and return ERROR_SUCCESS to the caller.

3.1.4.4 WitnessrAsyncNotify (Opnum 3)

The WitnessrAsyncNotify method is used by the client to request notification of registered resource changes from the server.

```
DWORD WitnessrAsyncNotify(
       [in] handle_t Handle,
       [in] PCONTEXT_HANDLE_SHARED pContext,
       [out] PRESP ASYNC NOTIFY* pResp);
```

Handle: An RPC binding handle [C706].

pContext: A context handle of type PCONTEXT_HANDLE_SHARED, as specified in section 2.2.1.3, that identifies the client on the server.

pResp: A pointer to a PRESP_ASYNC_NOTIFY structure, as specified in section 2.2.2.4.

Return Values: Returns 0x00000000 (ERROR_SUCCESS) on success or a nonzero error code, as specified in [MS-ERREF] section 2.2. The most common error codes are listed in the following table.

Return value/code	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x000005AA ERROR_NO_SYSTEM_RESOURCES	Insufficient system resources exist to complete the requested service.
0x00000490 ERROR_NOT_FOUND	The specified resource name is not found.

The server MUST search for the **WitnessRegistration** in **WitnessRegistrationList**, where **WitnessRegistration.RegistrationKey** matches the *pContext* parameter.

If no matching entry is found, the server MUST fail the request and return the error code ERROR_NOT_FOUND.

If the matching entry is found, and **WitnessServiceVersion** is 0x00020000, the server MUST update **WitnessRegistration.LastUseTime** to the current time, and **WitnessRegistration.IsAsyncNotifyRegistered** to TRUE.

The server MUST wait until either **WitnessRegistration.PendingChangeNotifications** or **WitnessRegistration.PendingMoveNotification** are not empty.

If **WitnessRegistration.PendingChangeNotifications** is not empty, the server MUST construct a RESP_ASYNC_NOTIFY structure as follows:

- pResp.MessageType: MUST be set to RESOURCE_CHANGE_NOTIFICATION.
- pResp.MessageBuffer: MUST be set to a RESOURCE_CHANGE structure with the following values:
 - The **Length** field MUST be set to the size of the RESOURCE_CHANGE structure.
 - If the NewState of the Notification is UNAVAILABLE, the ChangeType field MUST be set to RESOURCE_STATE_UNAVAILABLE, else ChangeType MUST be set to RESOURCE STATE AVAILABLE.
 - The **ResourceName** field MUST be set to the **ResourceName** of the **Notification**.
 - If additional entries are present in WitnessRegistration.PendingChangeNotifications, the server MUST continue to add RESOURCE_CHANGE structures to the pResp.MessageBuffer, until no entries remain in the list.
- pResp.NumberOfMessages: MUST be set to the number of resources changed.
- *pResp.Length*: MUST be set to the length of the **MessageBuffer** field.

If the **WitnessRegistration.PendingMoveNotification** is not empty, the server MUST construct the structure as follows:

- pResp.MessageType: MUST be set to CLIENT_MOVE_NOTIFICATION.
- pResp.MessageBuffer: MUST be set to an IPADDR_INFO_LIST structure with the following values:
 - The Reserved field MUST be set to 0.
 - The IPAddrInstances field MUST be set to the number of available interfaces in InterfaceList for which Interface.InterfaceGroupName matches the Notification.ChangeIndication.
 - For each Interface matched, the server MUST construct an IPADDR_INFO structure as follows:
 - If Interface.State is AVAILABLE, then the IPADDR_ONLINE flag in the Flags field MUST be set. If Interface.State is UNAVAILABLE, then the IPADDR_OFFLINE flag in the Flags field MUST be set.
 - If Interface.IPv4Address is not empty, the IPV4 field MUST be set to Interface.IPv4Address, and IPADDR_V4 MUST be set in the Flags field.
 - If Interface.IPv6Address is not empty, the IPV6 field MUST be set to Interface.IPv6Address, and IPADDR_V6 MUST be set in the Flags field.
 - The IPADDR_INFO structure MUST be copied into the IPAddrInfo field.
 - The Length field MUST be set to the size of the IPADDR_INFO_LIST structure.
- pResp.NumberOfMessages: MUST be set to 1.
- pResp.Length: MUST be set to the length of the MessageBuffer field.

If WitnessServiceVersion is 0x00020000, WitnessRegistration.WitnessClientVersion is 0x00020000, and WitnessRegistration.PendingShareMoveNotification is not empty, the server MUST construct the structure as follows:

- pResp.MessageType: MUST be set to SHARE MOVE NOTIFICATION.
- pResp.MessageBuffer: MUST be set to an IPADDR INFO LIST structure with the following values:
 - The Reserved field MUST be set to 0.
 - The IPAddrInstances field MUST be set to the number of available interfaces in InterfaceList for which Interface.InterfaceGroupName matches the Notification.Destination.
 - For each Interface matched, the server MUST construct an IPADDR_INFO structure as follows:
 - If Interface.IPv4Address is not empty, the IPV4 field MUST be set to Interface.IPv4Address, and IPADDR_V4 MUST be set in the Flags field.
 - If Interface.IPv6Address is not empty, the IPV6 field MUST be set to Interface.IPv6Address, and IPADDR_V6 MUST be set in the Flags field.
 - The IPADDR_INFO structure MUST be copied into the **IPAddrInfo** field.
 - The Length field MUST be set to the size of the IPADDR INFO LIST structure.
- pResp.NumberOfMessages: MUST be set to 1.

• *pResp.Length*: MUST be set to the length of the **MessageBuffer** field.

If WitnessServiceVersion is 0x00020000, WitnessRegistration.WitnessClientVersion is 0x00020000, and WitnessRegistration.PendingIPNotification is not empty, the server MUST construct the structure as follows:

- pResp.MessageType: MUST be set to IP_CHANGE_NOTIFICATION.
- pResp.MessageBuffer: MUST be set to an IPADDR_INFO_LIST structure with the following values:
 - The Reserved field MUST be set to 0.
 - The IPAddrInstances field MUST be set to the number of available interfaces in InterfaceList for which Interface.InterfaceGroupName matches the Notification.Destination.
 - For each Interface matched, the server MUST construct an IPADDR_INFO structure as follows:
 - If Interface.IPv4Address is not empty, the IPV4 field MUST be set to Interface.IPv4Address, and IPADDR_V4 MUST be set in the Flags field.
 - If Interface.IPv6Address is not empty, the IPV6 field MUST be set to Interface.IPv6Address, and IPADDR V6 MUST be set in the Flags field.
 - The IPADDR INFO structure MUST be copied into the IPAddrInfo field.
 - The **Length** field MUST be set to the size of the IPADDR_INFO_LIST structure.
- pResp.NumberOfMessages: MUST be set to 1.
- pResp.Length: MUST be set to the length of the MessageBuffer field.

The server MUST remove all entries that were processed from WitnessRegistration.PendingChangeNotifications, WitnessRegistration.PendingMoveNotification, WitnessRegistration.PendingShareMoveNotification, and WitnessRegistration.PendingIPNotification.

If **WitnessServiceVersion** is 0x00020000, the server MUST set **WitnessRegistration.LastUseTime** to the current time and **WitnessRegistration.IsAsyncNotifyRegistered** to FALSE.

The server MUST return ERROR_SUCCESS and the pResp parameter to the client.

3.1.4.5 WitnessrRegisterEx (Opnum 4)

The WitnessrRegisterEx method allows the witness client to register for resource state change notifications of a NetName, ShareName and multiple IPAddresses. The client can subsequently call the WitnessrAsyncNotify method to receive notifications when there is a state change on any of these resources.

```
DWORD WitnessrRegisterEx(
    [in] handle_t Handle,
    [out] PPCONTEXT_HANDLE ppContext,
    [in] ULONG Version,
    [in] [string] [unique] LPWSTR NetName,
    [in] [string] [unique] LPWSTR ShareName,
    [in] [string] [unique] LPWSTR IpAddress,
    [in] [string] [unique] LPWSTR ClientComputerName,
    [in] ULONG Flags,
```

Handle: An RPC binding handle [C706].

ppContext: A context handle of type PPCONTEXT_HANDLE, as specified in section 2.2.1.2, that identifies the client on the server.

Version: The version of the Witness protocol currently in use by the client.

NetName: A pointer to a null-terminated string that specifies the name of the resource for which the client requires notifications.

ShareName: A pointer to a null-terminated string that specifies the name of the share resource for which the client requires notifications.

IpAddress: A pointer to a null-terminated string that specifies the IP address to which the client application connection is established.

ClientComputerName: A pointer to a null-terminated string that is used to identify the Witness client.

Flags: The type of Witness registration. This field MUST be set to one of the following values:

Value	Meaning
WITNESS_REGISTER_NONE 0x00000000	If set, the client requests notifications only for the registered IP address.
WITNESS_REGISTER_IP_NOTIFICATION 0x00000001	If set, the client requests notifications of any eligible server IP addresses.

KeepAliveTimeout: The maximum number of seconds for any notification response from the server.

Return Values: Returns 0x00000000 (ERROR_SUCCESS) on success or a nonzero error code, as specified in [MS-ERREF] section 2.2. The most common error codes are listed in the following table.

Return value/code	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x000005AA ERROR_NO_SYSTEM_RESOURCES	Insufficient system resources exist to complete the requested service.
0x00000057 ERROR_INVALID_PARAMETER	The parameter is incorrect.
0x0000139F ERROR_INVALID_STATE	The specified resource state is invalid.
0x0000051A ERROR_REVISION_MISMATCH	The client request contains an invalid Witness protocol version.

This opnum is applicable only to servers that implement Witness protocol version 2.

If the **Version** field of the request is not 0x00020000, the server MUST stop processing the request and return the error code ERROR_REVISION_MISMATCH.

<u>If NetName</u>, <u>IpAddress</u>, or <u>ClientComputerName</u> is <u>NULL</u>, the server <u>MUST</u> fail the request and return the error code ERROR INVALID PARAMETER.

If the *NetName* parameter is not equal to **ServerGlobalName**, the server MUST fail the request and return the error code ERROR INVALID PARAMETER.

The server MUST search for an **Interface** in **InterfaceList**, where **Interface.IPv4Address** or **Interface.IPv6Address** matches the *IpAddress* parameter based on its format. If no matching entry is found, the server MUST fail the request and return the error code ERROR_INVALID_STATE.

If *ShareName* is not NULL, the server MUST enumerate the shares by calling *NetrShareEnum* as specified in [MS-SRVS] section 3.1.4.8. If the enumeration fails or if no shares are returned, the server MUST return the error code ERROR INVALID STATE.

If none of the shares in the list has shi*_type set to STYPE_CLUSTER_SOFS as specified in [MS-SRVS] section 3.1.4.8, the server MUST ignore **ShareName**.

Otherwise, the server MUST fail the request with the error code ERROR_INVALID_STATE for the following:

- **ShareName** does not exist in the enumerated list.
- The server MUST search for an **Interface** in **InterfaceList**, where **Interface.IPv4Address** or **Interface.IPv6Address** matches the *IpAddress* parameter based on its format. If no matching entry is found and **ShareName** has shi*_type set to STYPE_CLUSTER_SOFS, as specified in [MS-SRVS] section 2.2.2.4-, the server MUST fail the request with ERROR INVALID STATE.

The server MUST create a **WitnessRegistration** entry as follows and insert it into the **WitnessRegistrationList**.

- WitnessRegistration.WitnessClientVersion MUST be set to the value of the Version parameter.
- WitnessRegistration.WitnessClientName MUST be set to the ClientComputerName parameter.
- WitnessRegistration.LastUseTime MUST be set to the current time.
- WitnessRegistration.KeepAliveTime MUST be set to KeepAliveTimeout.
- WitnessRegistration.IsAsyncNotifyRegistered MUST be set to FALSE.
- WitnessRegistration.NetworkName MUST be set to the NetName parameter.
- WitnessRegistration.ShareName MUST be set to the ShareName parameter.
- If ShareName is not NULL, WitnessRegistration.ShareNameNotificationRequired MUST be set to TRUE; otherwise set to FALSE.
- If Flags field has WITNESS_REGISTER_IP_NOTIFICATION set,
 WitnessRegistration.IPNotificationRequired MUST be set to TRUE; otherwise set to FALSE.
- **WitnessRegistration.IPAddress** MUST be set to the *IPAddress* parameter.
- WitnessRegistration.RegistrationKey MUST be set to a newly generated UUID.
- WitnessRegistration.PendingChangeNotifications, WitnessRegistration.PendingMoveNotification,

WitnessRegistration.PendingShareMoveNotification, WitnessRegistration.PendingIPNotification MUST be set to empty.

The server MUST copy the **WitnessRegistration.RegistrationKey** into the *ppContext* parameter.

The server MUST return ERROR_SUCCESS and the ppContext parameter to the caller.

3.1.5 Timer Events

3.1.5.1 Unused Registration Timer Event

If the server implements version 2 of the protocol, it MUST implement this timer event.

When the Unused Registration Timer (section 3.1.2.1) expires, the server MUST search for the **WitnessRegistration** entry in **WitnessRegistrationList**. If

WitnessRegistration.IsAsyncNotifyRegistered is FALSE and **WitnessRegistration.LastUseTime** plus an implementation-specific time-out<5> is earlier than the current time, the server MUST remove the **WitnessRegistration** entry from the **WitnessRegistrationList**.

3.1.5.2 AsyncNotify Pending Timer Event

If the server implements version 2 of the protocol, it MUST implement this timer event.

When the Notification Pending Timer (section 3.1.2.2) expires, the server MUST search for the WitnessRegistration entry in WitnessRegistrationList. If WitnessRegistration.IsAsyncNotifyRegistered is TRUE and WitnessRegistration.LastUseTime plus WitnessRegistration.KeepAliveTime is earlier than the current time, the server MUST fail the

request with ERROR_TIMEOUT.

3.1.6 Other Local Events

The Service Witness Protocol is driven by a series of higher-layer triggered events in the following categories:

- A resource being enabled or disabled.
- A request for a client to move to another resource.
- The ownership of a share moving between resources.
- An IP address being added, removed, enabled, or disabled.

3.1.6.1 Server Application Notifies of an Interface Being Enabled or Disabled

The calling application provides the interface group name, IPv4 and/or IPv6 addresses, and state.

The server MUST search for the **Interface** in the **InterfaceList** where

Interface.InterfaceGroupName matches the application-provided interface group name, and Interface.IPv4Address or Interface.IPv6Address matches one or both of the application-provided IP addresses.

If a matching entry is found, the server MUST set **Interface.State** to the application-provided state. Then for each entry in the **WitnessRegistrationList** where **WitnessRegistration.NetworkName** matches the application-provided interface group name and **WitnessRegistration.IPAddress** matches the application-provided IP address, the server SHOULD<6> add a change entry to **WitnessRegistration.PendingChangeNotifications**, with a **ResourceName** of the **Interface.InterfaceGroupName** and a **NewState** of the application-provided state.

Else if no matching entry is found, the server MUST create a new **Interface** as follows, and add it to the **InterfaceList**:

- Interface.InterfaceGroupName: MUST be set to the application-provided interface group name.
- **Interface.State**: MUST be set to the application-supplied state.
- If the application supplied an IPv4 address, then Interface.IPv4Address MUST be set to it, else
 Interface.IPv4Address MUST be set to empty.
- If the application supplied an IPv6 address, then Interface.IPv6Address MUST be set to it, else Interface.IPv6Address MUST be set to empty.

The server MUST awaken any pending client requests awaiting notification in sections 3.1.4.1 and 3.1.4.4.

3.1.6.2 Server Application Notifies of a Request to Move to a New Resource

The calling application provides the Witness client name and resource name. The resource name can be an interface group name, an IP address, or a host name.

The server MUST search for all **WitnessRegistrations** in the **WitnessRegistrationList** where **WitnessRegistration.WitnessClientName** matches the application-provided witness client name.

For each **WitnessRegistration** matched, the server MUST create or overwrite the move entry in **WitnessRegistration.PendingMoveNotification**, setting the **Notification.Destination** to the application-provided resource name.

The server MUST awaken any client requests awaiting notification in section 3.1.4.4.

3.1.6.3 Server Application Notifies of a Change in the Resource that Owns a Share

This notification is applicable only to servers implementing version 2 (0x00020000). The calling application provides the Witness client name, share name, and resource name. The resource name can be an interface group name, an IP address, or a host name.

The server MUST search for all **WitnessRegistrations** in the **WitnessRegistrationList** where **WitnessRegistration.WitnessClientName** matches the application-provided witness client name, **WitnessRegistration.ShareName** matches the application-provided share name, and **WitnessRegistration.ShareNameNotificationRequired** is TRUE.

For each **WitnessRegistration** matched, the server MUST create or overwrite the share move entry in **WitnessRegistration.PendingShareMoveNotification**, setting the **Notification.Destination** to the application-provided resource name.

The server MUST awaken any client requests awaiting notification in section 3.1.4.4.

3.1.6.4 Server Application Notifies of an IP Address Being Added, Removed, Enabled or Disabled

This notification is applicable only to servers implementing version 2 (0x00020000). The calling application provides the Witness client name and resource name. The resource name can be an interface group name, an IP address, or a host name.

The server MUST search for all **WitnessRegistrations** in the **WitnessRegistrationList** where WitnessRegistration.WitnessClientName matches the application-provided witness client name and **WitnessRegistration.IPNotificationRequired** is TRUE.

For each WitnessRegistration matched, the server MUST create or overwrite the move entry in **WitnessRegistration.PendingIPNotification**, setting the **Notification.ChangeIndication** to the application-provided resource name.

The server MUST awaken any client requests awaiting notification in section 3.1.4.4.

3.1.6.5 Transport Connection Shutdown

When the RPC transport indicates that an RPC connection with a client has timed out, as specified in [MS-RPCE] section 3.3.3.2.1, the server MUST delete the **WitnessRegistration** entry for that client from the **WitnessRegistrationList**.

3.2 Witness Client Details

The client performs requests made to it by the application.

3.2.1 Abstract Data Model

This section describes a conceptual model of possible data organization that an implementation maintains to participate in this protocol. The organization is provided to facilitate the explanation of how the protocol behaves. This specification does not mandate that implementations adhere to this model as long as their external behaviors are consistent with that described in this specification.

3.2.1.1 Global

The client implements the following properties:

- **WitnessRegistrationList**: A list of **WitnessRegistration** initiated by the client to the witness servers. The structure of registration is as specified in section 3.2.1.2.
- **WitnessClientVersion**: The highest Witness protocol version supported by the Witness client. The value MUST be one of those listed in section 1.7.

3.2.1.2 Per WitnessRegistration

The client implements the following properties per witness registration.

- WitnessServerName: A null-terminated string that contains the name of the server.
- IPAddress: An IP address of a connection target.
- **RegistrationKey**: A unique value assigned by the server for this registration, in the form of context handle, as specified in section 2.2.1.1.
- **RPCHandle**: An RPC handle to be used for making requests of the Witness server.
- **WitnessNotifyRequest**: A Boolean indicating whether a WitnessrAsyncNotify request is outstanding.

If the client implements version 2 (0x00020000) of the Witness protocol, the client implements the following properties:

- ShareName: A null-terminated string that contains the share name.
- NetNameNotificationRequired: A Boolean when set; indicates that this registration requires notifications based on the NetName.

- **ShareNameNotificationRequired**: A Boolean when set; indicates that this registration requires notifications based on the *ShareName*.
- **IPNotificationRequired**: A Boolean when set; indicates that this registration requires notifications based on the IP address changes on the server associated with *NetName*.
- **WitnessServerVersion**: The Witness protocol version supported by the Witness server for this registration.

3.2.2 Timers

The client uses non-default behavior for the RPC Call Timeout timer defined in [MS-RPCE] section 3.3.2.2.2. The timer value that the client uses is implementation-specific.<7>

3.2.3 Initialization

The client MUST initialize WitnessRegistrationList to empty.

The client MUST initialize WitnessClientVersion in an implementation-specific manner<8>.

3.2.4 Message Processing Events and Sequencing Rules

After the client is initialized, it is subsequently driven by the higher-layer events triggered by the applications. The following sections describe events triggered by the higher layer.

3.2.4.1 Application Requests Witness Register

The caller provides the following:

- **NetName**: The name that the application is requesting for notifications, typically the name to which it has connected.
- **IpAddress**: The IP address for which the application requires receiving asynchronous notification.
- **ShareName**: A string containing the share name on which the application had requested for notifications, typically the share name to which it has connected. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsNetNameNotificationRequired**: A Boolean when set; indicates that the application is requesting witness registration for receiving notifications based on the **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsShareNameNotificationRequired**: A Boolean when set; indicates that the application is requesting witness registration for receiving notifications based on the **ShareName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsIPNotificationRequired**: A Boolean when set; indicates that the application is requesting witness registration for receiving notifications based on the IP addresses changes on the server associated with **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.

If the **NetName** parameter is an IPv4 address as dotted-decimal with four parts or an IPv6 address as 8 hexadecimal numbers separated by colons, the client MUST return an implementation-specific error to the calling application.

The client MUST establish an RPC connection to the Witness Service running on the **IPAddress**, as specified in section 2.1 using implementation-specific<9> values for authentication level and

authentication service. If the connection is not established, the resulting error MUST be returned to the caller.

The client MUST call the **WitnessrGetInterfaceList** method, by providing the RPC handle returned from the previous step as the *Handle* input parameter, and subsequently close the RPC handle. If the server returns an error, the client MUST return the same error code to the caller.

If the server returns STATUS_SUCCESS, the client MUST select an Interface returned in the WITNESS_INTERFACE_LIST where the INTERFACE_WITNESS flag is set in the **Flags** field and **State** is AVAILABLE.

If WitnessClientVersion is 0x00020000, the client MUST create a new WitnessRegistration entry in WitnessRegistrationList and set WitnessRegistration.WitnessServerVersion to the Version value returned in the WitnessrGetInterfaceList response and set WitnessRegistration.IpAddress to the *IpAddress*.

The client MUST establish an RPC Connection to the Witness Service running on the selected Interface, as specified in section 2.1 using implementation-specific<10> values for authentication level and authentication service. If the **IPv4** flag is set, the address in **Interface.IPv4** SHOULD be used for the connection. If the **IPv6** flag is set, the address in **Interface.IPv6** SHOULD be used for the connection. If the connection is not established, the resulting error MUST be returned to the caller.

If WitnessClientVersion is 0x00020000, and if IsShareNameNotificationRequired or IsIPNotificationRequired provided by the application is TRUE, the client MUST call the RPC WitnessrRegisterEx method on the resulting RPC handle, providing the following values:

- WitnessClientVersion for the Version parameter
- **NetName** for the *NetName* parameter
- **ShareName** for the *ShareName* parameter
- IpAddress for the IpAddress parameter
- A name to be used to identify the client<11> for ClientComputerName
- If IsIPNotificationRequired is TRUE, 0x00000001 for Flags; otherwise 0x00000000 for Flags.
- An implementation-specific time out value for the KeepAliveTimeout parameter.<12>

If the server returns an error, the client MUST retry the registration using other entries returned by the server for the **WitnessrGetInterfaceList** response. If all the entries are exhausted, the client MUST again call the **WitnessrGetInterfaceList** method as specified earlier. The client SHOULD<13> retry this registration sequence until it gets STATUS_SUCCESS from the server. If the server returns STATUS_SUCCESS, the client MUST update **WitnessRegistration** entry with the following values:

- WitnessServerName: This value MUST be set to the *NetName* parameter.
- **ShareName**: This value MUST be set to *ShareName* parameter.
- **RegistrationKey**: This value MUST be set to the value in the *ppContext* parameter.
- **RPCHandle**: This value MUST be set to the RPC handle used in the previous step.
- WitnessNotifyRequest: This value MUST be set to FALSE.
- NetNameNotificationRequired: This value MUST be set to TRUE.
- **ShareNameNotificationRequired**: This value MUST be set to TRUE if **IsShareNameNotificationRequired** is TRUE; otherwise set to FALSE.

 IPNotificationRequired: This value MUST be set to TRUE if IsIPNotificationRequired is TRUE; otherwise set to FALSE.

Otherwise, the client MUST call the RPC **WitnessrRegister** method on the resulting RPC handle, providing 0x00010001 for **Version**, **NetName**, **IpAddress**, and a name to be used to identify the client<14>, as input parameters. If the server returns an error, the client MUST retry the registration using other entries returned by the server for the **WitnessrGetInterfaceList** response. If all the entries are exhausted, the client MUST again call the **WitnessrGetInterfaceList** method as specified earlier. The client SHOULD<15> retry this registration sequence until it gets STATUS_SUCCESS from the server. If the server returns STATUS_SUCCESS, the client MUST create a new **WitnessRegistration** entry with the following values, insert the entry in **WitnessRegistrationList**, and return success to the caller:

- WitnessServerName: This value MUST be set to the NetName parameter.
- **IPAddress:** This value MUST be set to the *IpAddress* parameter.
- RegistrationKey: This value MUST be set to the value in the ppContext parameter.
- WitnessNotifyRequest: This value MUST be set to FALSE.
- **RPCHandle:** This value MUST be set to the RPC handle used in the previous step.
- If WitnessClientVersion is 0x00020000, ShareName MUST be set to NULL,
 NetNameNotificationRequired MUST be set to TRUE, ShareNameNotificationRequired MUST be set to FALSE, and IPNotificationRequiredRequired MUST be set to FALSE.

The client MUST return success to the caller.

3.2.4.2 Application Requests Witness Event Notification

The caller provides the following:

- **NetName**: The name that the application is requesting for notifications, typically the name to which it has connected.
- IpAddress: The IP address for which the application requires receiving asynchronous notification.
- **ShareName**: A string containing the share name that the application is requesting for notifications, typically the share name to which it has connected. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsNetNameNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsShareNameNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the **ShareName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsIPNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the IP addresses changes on the server associated with **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.

If WitnessClientVersion is 0x00020000, the client MUST locate the WitnessRegistration entry in the WitnessRegistrationList where WitnessRegistration.WitnessServerName matches NetName, WitnessRegistration.WitnessShareName matches ShareName, WitnessRegistration.IPAddress matches IPAddress, WitnessRegistration.NetNameNotificationRequired matches IsNetNameNotificationRequired,

WitnessRegistration.ShareNameNotificationRequired matches
IsShareNameNotificationRequired, and WitnessRegistration.IPNotificationRequired matches
IsIPNotificationRequired.

If WitnessClientVersion is 0x00010001, the client MUST locate a WitnessRegistration entry in the WitnessRegistrationList where WitnessRegistration.WitnessServerName matches the application-provided NetName and WitnessRegistration.IPAddress matches the application-provided IPAddress.

If no matching entry is found, or if the **WitnessRegistration.WitnessNotifyRequest** is TRUE, the client MUST stop processing and return an implementation-defined local error to the caller.

The client MUST set **WitnessRegistration.WitnessNotifyRequest** to TRUE.

The client MUST call the **WitnessrAsyncNotify** method, on **WitnessRegistration.RPCHandle**, passing **WitnessRegistration.RegistrationKey** as *pContext*.

When the server replies, if **WitnessClientVersion** is 0x00020000 and the status indicates ERROR TIMEOUT, the client MUST call the **WitnessrAsyncNotify** method as specified earlier.

Otherwise, the client MUST set WitnessRegistration.WitnessNotifyRequest to FALSE.

The status and any received RESP_ASYNC_NOTIFY result obtained from the server in the previous step MUST be returned to the caller.

3.2.4.3 Application Requests Witness UnRegister

The caller provides the following:

- **NetName**: The name that the application is requesting to be unregistered, typically the name to which it has previously registered.
- **IpAddress**: The IP address on which the application previously registered for receiving asynchronous notification.
- **ShareName**: A string containing the share name that the application is requesting for notifications, typically the share name to which it has connected. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsNetNameNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsShareNameNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the **ShareName**. This parameter is only applicable for clients implementing Witness protocol version 2.
- **IsIPNotificationRequired**: A Boolean when set; indicates that the application had requested witness registration for receiving notifications based on the IP addresses changes on the server associated with **NetName**. This parameter is only applicable for clients implementing Witness protocol version 2.

If WitnessClientVersion is 0x00020000, the client MUST locate the WitnessRegistration entry in the WitnessRegistrationList where WitnessRegistration.WitnessServerName matches NetName, WitnessRegistration.WitnessShareName matches ShareName, WitnessRegistration.IPAddress matches IPAddress, WitnessRegistration.NetNameNotificationRequired matches IsNetNameNotificationRequired,

WitnessRegistration.ShareNameNotificationRequired matches
IsShareNameNotificationRequired, and WitnessRegistration.IPNotificationRequired matches
IsIPNotificationRequired.

If WitnessClientVersion is 0x00010001, the client MUST locate a WitnessRegistration entry in the WitnessRegistrationList where WitnessRegistration.WitnessServerName matches the application-provided NetName and WitnessRegistration.IPAddress matches the application-provided IPAddress.

If no matching entry is found, or if the **WitnessRegistration.WitnessNotifyRequest** is TRUE, the client MUST stop processing and return an implementation-defined local error to the caller.

The client MUST call the WitnessrUnRegister method, on the **WitnessRegistration.RPCHandle**, passing the **WitnessRegistration.RegistrationKey** as the context.

If the server returns an error, the client MUST return the same error code to the caller. If the server returns STATUS_SUCCESS, the client MUST close **WitnessRegistration.RPCHandle**, remove the **WitnessRegistration** from **WitnessRegistrationList**, and return STATUS SUCCESS to the caller.

3.2.5 Timer Events

Upon the expiration of RPC Call Timeout Timer, as specified in section 3.2.2, the client MUST close the RPC connection to the server and release the binding handle.

3.2.6 Other Local Events

None.

4 Protocol Examples

The following section describes common scenarios that indicate normal traffic flow in order to illustrate the function of the Service Witness Protocol.

4.1 Registering Notification Changes from the Witness Server

The following diagram demonstrates the steps taken to register and unregister the client to receive notification changes from the server.




Figure 2: Message sequence used to register and unregister for notifications

- 1. The client sends a WitnessrGetInterfaceList request to the SMB3 Fileserver.
- 2. The SMB3 Fileserver returns information about the witness interfaces to which client connections can be made.

```
SWN: WitnessrGetInterfaceList Response, ReturnValue=0
InterfaceList:
    WitnessInterfaceListPtr: Pointer To 0x00020000
    ReferentID: 0x00020000
    WitnessInterfaceList:
        NumberOfInterfaces: 2 (0x2)
    WitnessInterfaceInfoPtr: Pointer To 0x00020004
        ReferentID: 0x00020004
    InterfaceInfo:
```

```
Size: 2 Elements
                 MaxCount: 2
             Element:
                 InterfaceGroupName: NODE02
                 padding: 0 Bytes
                 Version: 4294967295 (0xFFFFFFF)
                 State: 1 (0x1)
             padding1: 2 Bytes
                 Padding: Binary Large Object (2 Bytes)
                 IPV4: 192.168.1.22
                 IPV6: 0:0:0:0:0:0:0:0
             padding2: 0 Bytes
             Flags: 5 (0x5)
             Element:
                 InterfaceGroupName: NODE01
                 padding: 0 Bytes
                 Version: 4294967295 (0xFFFFFFFF)
                 State: 1 (0x1)
             padding1: 2 Bytes
                 Padding: Binary Large Object (2 Bytes)
                 IPV4: 192.168.1.12
                 IPV6: 0:0:0:0:0:0:0:0
             padding2: 0 Bytes
             Flags: 1 (0x1)
ReturnValue: 0 (0x0)
```

3. The client selects any one interface from the interface list and sends a **WitnessrRegister** request to register for resource state change notifications of NetName and IPAddress.

```
SWN: WitnessrRegister Request, Version=65537, NetName=generalfs, IpAddress=192.168.1.200,
ClientComputerName=CLIENT01.contoso.com
    Version: 65537 (0x10001)
    NetName: generalfs
        Pointer: Pointer To 0x00020000
           ReferentID: 0x00020000
        stringValue: generalfs
        Length: 10 Elements
            MaxCount: 10
            Offset: 0
            ActualCount: 10
        Array: generalfs
           ArrayData: generalfs
        IpAddress: 192.168.1.200
            Pointer: Pointer To 0x00020004
               ReferentID: 0x00020004
            stringValue: 192.168.1.200
               Length: 14 Elements
               MaxCount: 14
               Offset: 0
               ActualCount: 14
            Array: 192.168.1.200
            ArrayData: 192.168.1.200
        ClientComputerName: CLIENT01.contoso.com
              Pointer: Pointer To 0x00020008
                  ReferentID: 0x00020008
              stringValue: CLIENT01.contoso.com
              Length: 21 Elements
              MaxCount: 21
              Offset: 0
              ActualCount: 21
              Array: CLIENT01.contoso.com
                  ArrayData: CLIENT01.contoso.com
```

4. The Witness server processes the request and returns a context handle that identifies the client on the server.

```
SWN: WitnessrRegister Response, Context=0x1, ReturnValue=0
    Context: 0x1
    ContextType: 0 (0x0)
    ContextUuid: {8FC957B7-6C9B-9790-496A-F8A0F2193318}
    ReturnValue: 0 (0x0)
```

5. The client sends a **WitnessrAsyncNotify** request to receive asynchronous notifications of registered resource changes from the server.

```
SWN: WitnessrAsyncNotify Request, Context=0x1
    Context: 0x1
    ContextType: 0 (0x0)
    ContextUuid: {8FC957B7-6C9B-9790-496A-F8A0F2193318}
```

6. Whenever there is a state change on the registered resource, the Witness server responds to the client with a **WitnessrAsyncNotify** response.

```
SWN: WitnessrAsyncNotify Response, Resource Change Notification, ReturnValue=0
         RespAsyncNotifyPtr: Pointer To 0x00020000
             ReferentID: 0x00020000
         RespAsyncNotify:
            MessageType: 1 (0x1)
             Length: 28 (0x1C)
             NumberOfMessages: 1 (0x1)
         NotificationPtr: Pointer To 0x00020004, 28 Elements
             ReferentID: 0x00020004
             MaxCount: 28
         Notification:
             ResourceChange:
                Length: 28 (0x1C)
                 ChangeType: 255 (0xFF)
                ResourceName: GENERALFS
         pad: 0 Bytes
         ReturnValue: 0 (0x0)
```

7. The client sends a context handle in a **WitnessrUnRegister** request to unregister for notifications from the Witness server.

```
SWN: WitnessrUnRegister Request, Context=0x1
    Context: 0x1
    ContextType: 0 (0x0)
    ContextUuid: {8FC957B7-6C9B-9790-496A-F8A0F2193318}
```

8. The Witness server processes the requests by removing the entry and no longer notifies the client of resource state changes.

```
SWN: WitnessrUnRegister Response, ReturnValue=0
    ReturnValue: 0 (0x0)
```

5 Security

5.1 Security Considerations for Implementers

This protocol allows any user to connect to the server; therefore, any security weakness in the server implementation could be exploitable. The server implementation should ought to each method.

5.2 Index of Security Parameters

This protocol allows any user to establish a connection to the RPC server as specified in section 2.1.

6 Appendix A: Full IDL

For ease of implementation the full IDL is provided below, where "ms-dtyp.idl" refers to the IDL found in [MS-DTYP] Appendix A. The syntax uses the IDL syntax extensions defined in [MS-RPCE] section 2.2.4 and 3.1.1.5.1. For example, as noted in [MS-RPCE] section 2.2.4.9, a pointer_default declaration is not required and pointer_default(unique) is assumed.

The **MessageBuffer** field in the RESP_ASYNC_NOTIFY structure contains either a RESOURCE_CHANGE or an IPADDR_INFO_LIST structure. See sections 2.2.2.3 and 2.2.2.2 for details.

```
import "ms-dtyp.idl";
typedef [context handle] void * PCONTEXT HANDLE;
typedef [context_handle] PCONTEXT HANDLE PCONTEXT HANDLE SHARED;
typedef [ref] PCONTEXT HANDLE * PPCONTEXT HANDLE;
typedef struct RESP ASYNC NOTIFY {
    UINT MessageType;
    UINT Length;
    UINT NumberOfMessages;
    [size_is(Length)] [unique] PBYTE MessageBuffer;
} RESP ASYNC NOTIFY, *PRESP ASYNC NOTIFY;
typedef struct WITNESS INTERFACE INFO {
    WCHAR InterfaceGroupName[260];
    ULONG Version;
    USHORT State;
    ULONG IPV4;
    USHORT IPV6[8];
    UINT Flags;
} WITNESS INTERFACE INFO, *PWITNESS INTERFACE INFO;
typedef struct WITNESS INTERFACE LIST {
    UINT NumberOfInterfaces;
    [size is(NumberOfInterfaces)] [unique] PWITNESS INTERFACE INFO InterfaceInfo;
} WITNESS INTERFACE LIST, *PWITNESS INTERFACE LIST;
[uuid(ccd8c074-d0e5-4a40-92b4-d074faa6ba28)]
[version(1.1)]
[pointer default(unique)]
interface Witness {
    DWORD WitnessrGetInterfaceList(
        [in] handle t Handle,
        [out] PWITNESS INTERFACE LIST * InterfaceList);
    DWORD WitnessrRegister(
        [in] handle t Handle,
        [out] PPCONTEXT HANDLE ppContext,
        [in] ULONG Version,
        [in] [string] [unique] LPWSTR NetName,
        [in] [string] [unique] LPWSTR IpAddress,
        [in] [string] [unique] LPWSTR ClientComputerName);
    DWORD WitnessrUnRegister(
        [in] handle t Handle,
        [in] PCONTEXT HANDLE pContext);
    DWORD WitnessrAsyncNotify(
        [in] handle t Handle,
        [in] PCONTEXT HANDLE SHARED pContext,
        [out] PRESP ASYNC NOTIFY * pResp);
    DWORD WitnessrRegisterEx(
        [in] handle t Handle,
        [out] PPCONTEXT_HANDLE ppContext,
        [in] ULONG Version,
        [in] [string] [unique] LPWSTR NetName,
        [in] [string] [unique] LPWSTR ShareName,
        [in] [string] [unique] LPWSTR IpAddress,
        [in] [string] [unique] LPWSTR ClientComputerName,
```

```
[in] ULONG Flags,
[in] ULONG KeepAliveTimeout);
};
```

7 Appendix B: Product Behavior

The information in this specification is applicable to the following Microsoft products or supplemental software. References to product versions include released service packs.

-Note: Some of the information in this section is subject to change because it applies to a preliminary product version, and thus may differ from the final version of the software when released. All behavior notes that pertain to the preliminary product version contain specific references to it as an aid to the reader.

- Windows 8 operating system
- Windows Server 2012 operating system
- Windows 8.1 operating system
- Windows Server 2012 R2 operating system
- Windows 10 operating system
- Windows Server 2016 Technical Preview operating system

Exceptions, if any, are noted below. If a service pack or Quick Fix Engineering (QFE) number appears with the product version, behavior changed in that service pack or QFE. The new behavior also applies to subsequent service packs of the product unless otherwise specified. If a product edition appears with the product version, behavior is different in that product edition.

Unless otherwise specified, any statement of optional behavior in this specification that is prescribed using the terms SHOULD or SHOULD NOT implies product behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that the product does not follow the prescription.

- <1> Section 2.2.2.1: Windows Server 2012, Windows Server 2012 R2, and Windows Server 2016 Technical Preview set the undefined **Flags** field bits to arbitrary values.
- <2> Section 3.1.3: Windows Server 2012 sets this value to 0x00010001. Windows Server 2012 R2 and Windows Server 2016 Technical Preview set this value to 0xFFFFFFFF.
- <3> Section 3.1.4: If the authentication level is not RPC_C_AUTHN_LEVEL_PKT_PRIVACY or RPC_C_AUTHN_LEVEL_PKT_INTEGRITY, Windows Server 2012, Windows Server 2012 R2, and Windows Server 2016 Technical Preview—will fail the call with ERROR ACCESS DENIED.

Windows Server 2012, Windows Server 2012 R2, and Windows Server 2016 Technical Preview will fail the call with ERROR_NOT_AUTHENTICATED if the authentication service is not equal to one of the following values:

- RPC C AUTHN GSS KERBEROS
- RPC_C_AUTHN_GSS_NEGOTIATE
- RPC C AUTHN WINNT
- <4> Section 3.1.4.3: Windows Server 2012 R2 and Windows Server 2016 Technical Preview fail the request with ERROR INVALID PARAMETER.
- <5> Section 3.1.5.1: Windows Server 2012 R2 and Windows Server 2016 Technical Preview server use a 30-second time-out.
- <6> Section 3.1.6.1: Windows Server will send a single notification for NetNames that are aliases of each other.

- <7> Section 3.2.2: Windows 8.1, Windows Server 2012 R2, Windows 10, and Windows Server 2016 Technical Preview—use a default of 180 seconds.
- <8> Section 3.2.3: Windows 8 and Windows Server 2012 clients set **WitnessClientVersion** to 0x00010001; Windows 8.1, Windows Server 2012 R2, Windows 10, and Windows Server 2016 Technical Preview—clients set **WitnessClientVersion** to 0x00020000.
- <9> Section 3.2.4.1: By default, Windows 8, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, Windows 10, and Windows Server 2016 Technical Preview set the authentication level to RPC_C_AUTHN_LEVEL_PKT_INTEGRITY and the authentication service to RPC_C_AUTHN_GSS_NEGOTIATE.
- <10> Section 3.2.4.1: By default, Windows 8, Windows Server 2012, Windows 8.1, Windows Server 2012 R2, Windows 10 and Windows Server 2016 Technical Preview set the authentication level to RPC_C_AUTHN_LEVEL_PKT_INTEGRITY and the authentication service to RPC_C_AUTHN_GSS_NEGOTIATE.
- <11> Section 3.2.4.1: Windows uses the **fully qualified domain name (FQDN)** of the local computer to identify the client.
- <12> Section 3.2.4.1: Windows 8.1, Windows Server 2012 R2, Windows 10, and Windows Server 2016 Technical Preview use a default **KeepAliveTime** value of 120 seconds.
- <13> Section 3.2.4.1: Windows clients retry the registration every 60 seconds.
- <14> Section 3.2.4.1: Windows uses the fully qualified domain name (FQDN) of the local computer to identify the client.
- <15> Section 3.2.4.1: Windows clients return the registration every 60 seconds.

8 Change Tracking

No table of This section identifies changes is available. The that were made to this document is either new or has had no changes since its the last release. Changes are classified as New, Major, Minor, Editorial, or No change.

The revision class **New** means that a new document is being released.

The revision class **Major** means that the technical content in the document was significantly revised. Major changes affect protocol interoperability or implementation. Examples of major changes are:

- A document revision that incorporates changes to interoperability requirements or functionality.
- The removal of a document from the documentation set.

The revision class **Minor** means that the meaning of the technical content was clarified. Minor changes do not affect protocol interoperability or implementation. Examples of minor changes are updates to clarify ambiguity at the sentence, paragraph, or table level.

The revision class **Editorial** means that the formatting in the technical content was changed. Editorial changes apply to grammatical, formatting, and style issues.

The revision class **No change** means that no new technical changes were introduced. Minor editorial and formatting changes may have been made, but the technical content of the document is identical to the last released version.

Major and minor changes can be described further using the following change types:

- New content added.
- Content updated.
- Content removed.
- New product behavior note added.
- Product behavior note updated.
- Product behavior note removed.
- New protocol syntax added.
- Protocol syntax updated.
- Protocol syntax removed.
- New content added due to protocol revision.
- Content updated due to protocol revision.
- Content removed due to protocol revision.
- New protocol syntax added due to protocol revision.
- Protocol syntax updated due to protocol revision.
- Protocol syntax removed due to protocol revision.
- Obsolete document removed.

Editorial changes are always classified with the change type **Editorially updated**.

Some important terms used in the change type descriptions are defined as follows:

- **Protocol syntax** refers to data elements (such as packets, structures, enumerations, and methods) as well as interfaces.
- **Protocol revision** refers to changes made to a protocol that affect the bits that are sent over the wire.

The changes made to this document are listed in the following table. For more information, please contact dochelp@microsoft.com.

Section	Tracking number (if applicable) and description	Major change (Y or N)	Change type
3.1.4.2 WitnessrRegister (Opnum 1)	72855 : Updated the processing rules for NetName, IpAddress, and ClientComputerName.	Y	Content update.
3.1.4.5 WitnessrRegisterEx (Opnum 4)	72855 : Updated the processing rules for NetName, IpAddress, and ClientComputerName.	Y	Content update.

9 Index

Α

```
Abstract data model
  client 29
    Witness 29
 server 15
    Witness 15
Applicability 7
Application Requests Witness Event Notification method 32
Application Requests Witness Register method 30
Application Requests Witness UnRegister method 33
Capability negotiation 8
Change tracking 43
Client
 abstract data model 29
 Application Requests Witness Event Notification method 32
 Application Requests Witness Register method 30
 Application Requests Witness UnRegister method 33
 initialization 30
 local events 34
 message processing 30
 overview 29
 sequencing rules 30
 timer events 34
 timers 30
  Witness
   abstract data model 29
   Application Requests Witness Event Notification method 32
   Application Requests Witness Register method 30
   Application Requests Witness UnRegister method 33
   initialization 30
   interface 29
   local events 34
   message processing 30
   sequencing rules 30
   timer events 34
   timers 30
 witness interface 29
Common data types 9
 structures 10
Data model - abstract
 client 29
    Witness 29
 server 15
   Witness 15
Data types
 common - overview 9
 PCONTEXT_HANDLE 10
 PCONTEXT_HANDLE_SHARED 10
  PPCONTEXT_HANDLE 10
Ε
Events
 local
```

```
client
      Witness 34
    server
      Witness 27
  local - client 34
  local - server 27
  timer
    client
      Witness 34
  timer - client 34
Examples
  overview 35
  registering notification changes from the witness server 35
F
Fields - vendor extensible 8
Full IDL 39
G
Glossary 5
Ι
IDL 39
Implementer - security considerations 38
Index of security parameters 38
Informative references 6
Initialization
  client 30
    Witness 30
  server 17
    Witness 17
Interfaces
  client
    Witness 29
  server
    Witness 15
Interfaces - client
  witness 29
Interfaces - server
  witness 15
Introduction 5
IPADDR_INFO_LISTstructure 11
IPADDR\_INFO structure~10
Local events
  client 34
    Witness 34
  server 27
    Witness 27
М
Message processing
  client 30
    Witness 30
  server 17
    Witness 17
Messages
  common data types 9
```

```
transport 9
Methods
 Application Requests Witness Event Notification 32
 Application Requests Witness Register 30
 Application Requests Witness UnRegister 33
 WitnessrAsyncNotify (Opnum 3) 21
 WitnessrGetInterfaceList (Opnum 0) 18
 WitnessrRegister (Opnum 1) 19
 WitnessrRegisterEx (Opnum 4) 24
 WitnessrUnRegister (Opnum 2) 21
Normative references 6
Overview (synopsis) 6
Parameters - security index 38
PCONTEXT HANDLE data type 10
PCONTEXT_HANDLE_SHARED data type 10
PPCONTEXT_HANDLE data type 10
Preconditions 7
Prerequisites 7
Product behavior 41
R
References 6
 informative 6
 normative 6
Registering notification changes from the witness server example 35
Relationship to other protocols 7
RESOURCE CHANGEstructure 12
RESP_ASYNC_NOTIFYstructure 12
S
Security
 implementer considerations 38
 parameter index 38
Sequencing rules
 client 30
   Witness 30
  server 17
 Witness 17
Server
 abstract data model 15
 initialization 17
 local events 27
 message processing 17
 overview 15
 sequencing rules 17
  Witness
   abstract data model 15
   initialization 17
   interface 15
   local events 27
   message processing 17
   PendingChangeNotifications 16
   PendingMoveNotification 16
```

```
Request to Move to a New Resource 28
   sequencing rules 17
   WitnessrAsyncNotify (Opnum 3) method 21
   WitnessrGetInterfaceList (Opnum 0) method 18
   WitnessrRegister (Opnum 1) method 19
   WitnessrRegisterEx (Opnum 4) method 24
   WitnessrUnRegister (Opnum 2) method 21
  witness interface 15
 WitnessrAsyncNotify (Opnum 3) method 21
 WitnessrGetInterfaceList (Opnum 0) method 18
 WitnessrRegister (Opnum 1) method 19
 WitnessrRegisterEx (Opnum 4) method 24
 WitnessrUnRegister (Opnum 2) method 21
Standards assignments 8
Structures
 IPADDR_INFO 10
 IPADDR_INFO_LIST 11
 overview 10
 RESOURCE_CHANGE 12
 RESP_ASYNC_NOTIFY 12
 WITNESS_INTERFACE_INFO 13
 WITNESS_INTERFACE_LIST 14
т
Timer events
  client 34
   Witness 34
Timers
  client 30
   Witness 30
Tracking changes 43
Transport 9
Vendor extensible fields 8
Versioning 8
W
Witness
 client - overview 29
 interface
   client 29
   server 15
 server - overview 15
witness interface (section 3.1 15, section 3.2 29)
WITNESS_INTERFACE_INFOstructure 13
```

WITNESS_INTERFACE_LISTstructure 14
WitnessrAsyncNotify (Opnum 3) method 21
WitnessrGetInterfaceList (Opnum 0) method 18
WitnessrRegister (Opnum 1) method 19
WitnessrRegisterEx (Opnum 4) method 24
WitnessrUnRegister (Opnum 2) method 21